
Stork

Release 1.16.0

Internet Systems Consortium

May 14, 2024

CONTENTS

1	Overview	3
1.1	Goals	3
1.2	Architecture	3
2	Installation	5
2.1	Supported Systems	5
2.2	Installation Prerequisites	5
2.3	Stork Tool	6
2.4	Preparing Stork Server Database	6
2.5	Installing From Packages	8
2.5.1	Installing the Stork Server	9
2.5.1.1	Installing on Debian/Ubuntu	9
2.5.1.2	Installing on CentOS/RHEL/Fedora	9
2.5.1.3	Setup	9
2.5.1.4	Stork UI Behind a Reverse Proxy	11
2.5.1.5	Securing the Database Connection	12
2.5.2	Installing the Stork Agent	12
2.5.2.1	Agent Configuration Settings	12
2.5.2.2	Logging Settings	14
2.5.2.3	Securing Connections Between the Stork Server and a Stork Agent	14
2.5.2.4	Securing Connections Between stork-agent and the Kea Control Agent	15
2.5.2.5	Installation From Cloudsmith and Registration With an Agent Token	16
2.5.2.6	Installation With a Script and Registration With a Server Token	17
2.5.2.7	Installation With a Script and Registration With an Agent Token	18
2.5.2.8	Installation From Cloudsmith and Registration With a Server Token	18
2.5.2.9	Registration Methods Summary	19
2.5.2.10	Agent Setup Summary	19
2.5.2.11	Inspecting Keys and Certificates	19
2.5.2.12	Using External Keys and Certificates	20
2.5.3	Installing the hooks	20
2.5.4	Upgrading	21
2.6	Installing From Sources	21
2.6.1	Compilation Prerequisites	21
2.6.2	Download Sources	21
2.6.3	Building	21
2.6.4	Installing on FreeBSD	22
2.6.5	Installing on OpenBSD	23
2.6.6	Cross-compilation	23
2.7	Integration With Prometheus and Grafana	24
2.7.1	Prometheus Integration	24

2.7.2	Alerting in Prometheus	25
2.7.3	Grafana Integration	26
2.7.4	Subnet Identification	26
2.7.5	Alerting in Grafana	26
3	Using Stork	29
3.1	Managing Users	29
3.2	Changing a User Password	29
3.3	Configuration Settings	30
3.4	Connecting and Monitoring Machines	30
3.4.1	Monitoring a Machine	30
3.4.2	Disconnecting From a Machine	30
3.4.3	Dumping Diagnostic Information Into a File	31
3.5	Monitoring Applications	31
3.5.1	Application Status	31
3.5.2	Friendly App Names	32
3.5.3	IPv4 and IPv6 Subnets per Kea Application	32
3.5.4	IPv4 and IPv6 Subnets in the Whole Network	33
3.5.5	IPv4 and IPv6 Networks	33
3.5.6	Host Reservations	33
3.5.6.1	Listing Host Reservations	33
3.5.6.2	Host Reservation Usage Status	34
3.5.6.3	Sources of Host Reservations	35
3.5.6.4	Creating Host Reservations	35
3.5.6.5	Updating Host Reservations	36
3.5.6.6	Deleting Host Reservations	36
3.5.7	Leases Search	37
3.5.8	Kea High Availability Status	37
3.5.9	Viewing the Kea Log	38
3.5.10	Viewing the Kea Configuration as a JSON Tree	39
3.5.11	Configuration Review	40
3.5.12	Synchronizing Kea Configurations	40
3.6	Dashboard	41
3.6.1	DHCP Panel	41
3.6.2	Events Panel	41
3.7	Events Page	41
4	Troubleshooting	43
4.1	stork-agent	43
4.2	stork-server	49
5	Backend API	53
6	Demo	55
6.1	Requirements	55
6.2	Setup Steps	56
6.2.1	Premium Features	56
6.2.2	Detached Mode	56
6.3	Demo Containers	56
6.4	Initialization	58
6.5	Stork Environment Simulator	58
6.6	Prometheus	58
6.7	Grafana	59
7	Manual Pages	61

7.1	<code>stork-server</code> - Main Stork Server	61
7.1.1	Synopsis	61
7.1.2	Description	61
7.1.3	Arguments	61
7.1.4	Mailing Lists and Support	64
7.1.5	History	64
7.1.6	See Also	64
7.2	<code>stork-agent</code> - Stork Agent to Monitor BIND 9 and Kea services	64
7.2.1	Synopsis	64
7.2.2	Description	64
7.2.3	Arguments	64
7.2.4	Registration	66
7.2.5	Mailing Lists and Support	66
7.2.6	History	66
7.2.7	See Also	66
7.3	<code>stork-tool</code> - A Tool for Managing Stork Server	66
7.3.1	Synopsis	66
7.3.2	Description	66
7.3.3	Certificate Management	67
7.3.4	Database Creation	68
7.3.4.1	Examples	68
7.3.5	Database Migration	69
7.3.6	Common Options	69
7.3.7	Mailing Lists and Support	70
7.3.8	History	71
7.3.9	See Also	71

Stork is an open source monitoring application and dashboard for ISC's Kea DHCP, and eventually for ISC's BIND 9. It is the spiritual successor of the earlier projects Kittiwake and Anterius.



This is the developer's guide for Stork version 1.16.0 and is aimed at Stork developers, external contributors, and anyone who wants to understand the internal operation of Stork. Programming background is assumed.

For the user's guide, see the *Stork Administrator Reference Manual*. Links to the most up-to-date version of the Stork ARM document, along with other documents for Stork, can be found on ISC's [Stork project homepage](#) or at [Read the Docs](#).

OVERVIEW

1.1 Goals

The goals of the ISC Stork project are:

- To provide monitoring and insight into Kea DHCP operations.
- To provide alerting mechanisms that indicate failures, fault conditions, and other unwanted events in Kea DHCP services.
- To permit easier troubleshooting of these services.


Although Stork currently only offers monitoring, insight, and alerts for Kea DHCP, we plan to add similar capabilities for BIND 9 in future versions.

1.2 Architecture

Stork is comprised of two components: the Stork server (**stork-server**) and the Stork agent (**stork-agent**).

The Stork server is installed on a stand-alone machine. It connects to any indicated agents and indirectly (via those agents) interacts with the Kea DHCP services. It provides an integrated, centralized front end for these services. Only one Stork server is deployed in a network.

The Stork agent is installed along with Kea DHCP and interacts directly with those services. There may be many agents deployed in a network, one per machine.



INSTALLATION

Stork can be installed from pre-built packages or from sources; the following sections describe both methods. Unless there is a good reason to compile from sources, installing from native deb or RPM packages is easier and faster.

2.1 Supported Systems

Stork is tested on the following systems:

- Ubuntu 18.04 and 20.04
- Fedora 31 and 32
- CentOS 8
- MacOS 11.3*

* MacOS is not and will not be officially supported. However, many developers on ISC's team use Macs, so the intention is to keep Stork buildable on this platform.

`stork-server` and `stork-agent` are written in the Go language; the server uses a PostgreSQL database. In principle, the software can be run on any POSIX system that has a Go compiler and PostgreSQL. It is likely the software can also be built on other modern systems, but ISC's testing capabilities are modest. We encourage users to try running Stork on other OSes not on this list and report their findings to ISC.

2.2 Installation Prerequisites

The Stork agent does not require any specific dependencies to run. It can be run immediately after installation.

Stork uses the `status-get` command to communicate with Kea.

Stork requires the premium Host Commands (`host_cmds`) hook library to be loaded by the Kea instance to retrieve host reservations stored in an external database. Stork works without the Host Commands hook library, but is not able to display host reservations. Stork can retrieve host reservations stored locally in the Kea configuration without any additional hook libraries.

Stork requires the open source Statistics Commands (`stat_cmds`) hook library to be loaded by the Kea instance to retrieve lease statistics. Stork works without the Stat Commands hook library, but is not able to show pool utilization and other statistics.

Stork uses Go implementation to handle TLS connections, certificates, and keys. The secrets are stored in the PostgreSQL database, in the `secret` table.

For the Stork server, a PostgreSQL database (<https://www.postgresql.org/>) version 10 or later is required. Stork will attempt to run with older versions, but may not work correctly. The general installation procedure for PostgreSQL is

OS-specific and is not included here. However, please note that Stork uses `pgcrypto` extensions, which often come in a separate package. For example, a `postgresql-crypto` package is required on Fedora and `postgresql12-contrib` is needed on RHEL and CentOS.

2.3 Stork Tool

The **Stork Tool** is a program installed with the **Stork Server**, providing commands to set up server's database and manage TLS certificates. Using this tool is facultative because the server runs the database migrations and creates suitable certificates at startup on its own. However, the tool provides useful commands for inspecting the current database schema version and downgrading to one of the previous versions. In addition, in the [Preparing Stork Server Database](#) section it is described how the tool can be conveniently used to create a new database and its credentials without a need to run SQL commands directly using the `psql` program.

The [Inspecting Keys and Certificates](#) section describes how to use the tool for TLS certificates management.

Further sections describe different methods for installing the Stork Server from packages. See: [Installing on Debian/Ubuntu](#) and [Installing on CentOS/RHEL/Fedora](#). The `stork-tool` program is installed from the packages together with the server. Alternatively, the tool can be built from sources:

```
$ rake build:tool
```

Please refer to the manual page for usage details: [stork-tool - A Tool for Managing Stork Server](#).

2.4 Preparing Stork Server Database

Before running **Stork Server**, a PostgreSQL database and the user with suitable privileges must be created. Using the `stork-tool` is the most convenient way to set up the database.

The following command creates a new database `stork` and a user `stork` with all privileges in this database. It also installs the `pgcrypto` extension required by the Stork Server.

```
$ stork-tool db-create --db-name stork --db-user stork
created database and user for the server with the following credentials database_
↪name=stork password=L82B+kJE0yhDoMnZf9qPAGyKjH5Qo/Xb user=stork
```

By default, `stork-tool` connects to the database as user `postgres`, a default admin role in many PostgreSQL installations. If an installation uses a different administrator name, it can be specified with the `--db-maintenance-user` option. For example:

```
$ stork-tool db-create --db-maintenance-user thomson --db-name stork --db-user stork
created database and user for the server with the following credentials database_
↪name=stork password=L82B+kJE0yhDoMnZf9qPAGyKjH5Qo/Xb user=stork
```

Similarly, a `postgres` database should often exist in a PostgreSQL installation. However, a different maintenance database can be selected with the `--db-maintenance-name` option.

The `stork-tool` generates a random password to the created database. This password needs to be copied into the server environment file or used in the `stork-server` command line to configure the server to use this password while connecting to the database. Use the `--db-password` option with the `db-create` command to create a user with a specified password.

It is also possible to create the database manually (i.e., using the `psql` tool).

First, connect to PostgreSQL using `psql` and the `postgres` administration user. Depending on the system's configuration, it may require switching to the user `postgres` first, using the `su postgres` command.

```
$ psql postgres
psql (11.5)
Type "help" for help.
postgres=#
```

Then, prepare the database:

```
postgres=# CREATE USER stork WITH PASSWORD 'stork';
CREATE ROLE
postgres=# CREATE DATABASE stork;
CREATE DATABASE
postgres=# GRANT ALL PRIVILEGES ON DATABASE stork TO stork;
GRANT
postgres=# GRANT ALL PRIVILEGES ON SCHEMA public TO stork;
GRANT
postgres=# \c stork
You are now connected to database "stork" as user "postgres".
stork=# create extension pgcrypto;
CREATE EXTENSION
```

Note: Make sure the actual password is stronger than “stork”, which is trivial to guess. Using default passwords is a security risk. Stork puts no restrictions on the characters used in the database passwords, nor on their length. In particular, it accepts passwords containing spaces, quotes, double quotes, and other special characters. Please also consider using the `stork-tool` to generate a random password.

To generate a random password run:

```
$ stork-tool db-password-gen
generated new database password          password=1qWVzmLKj/j40/FVsvjM2ylcFdaFfNxx
```

The newly created database is not ready for use until necessary database migrations are executed. The migrations create tables, indexes, triggers, and functions required by the Stork Server. As mentioned above, the server can automatically run the migrations at startup, bringing up the database schema to the latest version. However, if a user wants to run the migrations before starting the server, they can use the `stork-tool`:

```
$ stork-tool db-init
$ stork-tool db-up
```

The up and down commands have an optional `-t` parameter that specifies the desired schema version. It is useful when debugging database migrations or downgrading to one of the earlier Stork versions.

```
$ # migrate up version 25
$ stork-tool db-up -t 25
$ # migrate down back to version 17
$ stork-tool db-down -t 17
```

The server requires the latest database version to run, always runs the migration on its own, and refuses to start if the migration fails for any reason. The migration tool is mostly useful for debugging problems with migration, or for migrating the database without actually running the service. For the complete manual page, please see [stork-tool - A Tool for Managing Stork Server](#).

To debug migrations, another useful feature is SQL tracing using the `--db-trace-queries` parameter. The options are either “all” (trace all SQL operations, including migrations and runtime) or “run” (only trace runtime operations and skip migrations). If specified without any parameters, “all” is assumed. With it enabled, `stork-tool` prints out all its SQL queries on stderr. For example, these commands can be used to generate an SQL script that updates the schema. Note that for some migrations, the steps are dependent on the contents of the database, so this is not a universal Stork schema. This parameter is also supported by the Stork Server.

```
$ stork-tool db-down -t 0
$ stork-tool db-up --db-trace-queries 2> stork-schema.txt
```

2.5 Installing From Packages

Stork packages are stored in repositories located on the Cloudsmith service: <https://cloudsmith.io/~isc/repos/stork/packages/>. Both Debian/Ubuntu and RPM packages may be found there.

Detailed instructions for setting up the operating system to use this repository are available under the **Set Me Up** button on the Cloudsmith repository page.

A few command line tools are required for setting up the repository:

- `bash` to execute the `setup.*.sh` scripts that use bash-specific features like `==` inside the `test` expression, local variables, `function` keyword in function declarations.
- `curl` to fetch the `setup.*.sh` script itself, but also for actions carried out by the script like fetching GPG keys, checking if URLs are available, or fetching other scripts.
- `cut` for the output manipulation done by the script
- `gpg` for importing GPG keys in the script
- `sed` for various textual substitutions done by the script
- `sudo` for elevating privileges required by the package manager
- `apt-get` in case of a Debian-based distribution
- `rpm` in case of an RPM-based distribution
- one of `dnf`, `microdnf`, `yum`, `zypper` in case of an RPM-based distribution

Other command line tools may be required based on how the script evolves or based on what OS the script is running on:

- `grep` and `head` for filtering output
- `sort` for sorting output
- `fmt` and `xargs` for better reporting of errors
- `uname` to detect the OS the script is running on
- `python` and `pip` for a redundant way of automatically detecting the OS in case the main OS detection mechanism does not work

It is possible to install both `stork-agent` and `stork-server` on the same machine. It is useful in small deployments with a single monitored machine, to avoid setting up a dedicated system for the Stork server. In those cases, however, an operator must consider the potential impact of the `stork-server` on other services running on the same machine.

2.5.1 Installing the Stork Server

2.5.1.1 Installing on Debian/Ubuntu

The first step for both Debian and Ubuntu is:

```
$ curl -sLf 'https://dl.cloudsmith.io/public/isc/stork/cfg/setup/bash.deb.sh' | sudo   
↪ bash
```

Next, install the Stork server package:

```
$ sudo apt install isc-stork-server
```

2.5.1.2 Installing on CentOS/RHEL/Fedora

The first step for RPM-based distributions is:

```
$ curl -sLf 'https://dl.cloudsmith.io/public/isc/stork/cfg/setup/bash.rpm.sh' | sudo   
↪ bash
```

Next, install the Stork server package:

```
$ sudo dnf install isc-stork-server
```

If `dnf` is not available, `yum` can be used instead:

```
$ sudo yum install isc-stork-server
```

2.5.1.3 Setup

The following steps are common for Debian-based and RPM-based distributions using `systemd`.

Configure the Stork server settings in `/etc/stork/server.env`.

Note: The environment file **IS NOT** read by default if you run the Stork server manually (without using `systemd`). To load the environment variables from this file you should call the `. /etc/stork/server.env` command before executing the binary (in the same shell instance) or run Stork with the `--use-env-file` switch.

The following settings are required for the database connection (they have a common `STORK_DATABASE_` prefix):

- `STORK_DATABASE_HOST` - the address of a PostgreSQL database; the default is `localhost`
- `STORK_DATABASE_PORT` - the port of a PostgreSQL database; the default is `5432`
- `STORK_DATABASE_NAME` - the name of a database; the default is `stork`
- `STORK_DATABASE_USER_NAME` - the username for connecting to the database; the default is `stork`
- `STORK_DATABASE_PASSWORD` - the password for the username connecting to the database

Note: All of the database connection settings have default values, but we strongly recommend protecting the database with a non-default and hard-to-guess password in the production environment. The `STORK_DATABASE_PASSWORD` setting must be adjusted accordingly.

The remaining settings pertain to the server's RESTful API configuration (the `STORK_REST_` prefix):

- `STORK_REST_HOST` - the IP address on which the server listens
- `STORK_REST_PORT` - the port number on which the server listens; the default is **8080**
- `STORK_REST_TLS_CERTIFICATE` - a file with a certificate to use for secure connections
- `STORK_REST_TLS_PRIVATE_KEY` - a file with a private key to use for secure connections
- `STORK_REST_TLS_CA_CERTIFICATE` - a certificate authority file used for mutual TLS authentication

Providing the CA certificate path enables the TLS client certificate verification. Any HTTP request to the server assigned with a missing, invalid, or untrusted TLS certificate will be rejected.

- `STORK_REST_STATIC_FILES_DIR` - a directory with static files served in the user interface

The `STORK_REST_STATIC_FILES_DIR` should be set to `/usr/share/stork/www` for the Stork Server installed from the binary packages. It's the default location for the static content.

- `STORK_REST_BASE_URL` - the base URL of the UI

Specify this flag if the UI is served from a subdirectory (not the root URL). It must start and end with a slash. Example: `https://www.example.com/admin/stork/` would need to have `"/admin/stork/"` as the `rest-base-url`.

Note: The Stork agent must trust the REST TLS certificate presented by Stork server. Otherwise, the registration process fails due to invalid Stork Server certificate verification. We strongly recommend using proper, trusted certificates for security reasons. If you need to use a self-signed certificate (e.g., for deployment in the Docker environment), then you can add its CA certificate to the system certificates on the Stork agent machine. See [Stack Overflow thread and discussion in #859](#).

The remaining settings pertain to the server's Prometheus `/metrics` endpoint configuration (the `STORK_SERVER_` prefix is for general purposes):

- `STORK_SERVER_ENABLE_METRICS` - enable the Prometheus metrics collector and `/metrics` HTTP endpoint

Warning: The Prometheus `/metrics` endpoint does not require authentication. Therefore, securing this endpoint from external access is highly recommended to prevent unauthorized parties from gathering the server's metrics. One way to restrict endpoint access is by using an appropriate HTTP proxy configuration to allow only local access or access from the Prometheus host. Please consult the NGINX example configuration file shipped with Stork.

With the settings in place, the Stork server service can now be enabled and started:

```
$ sudo systemctl enable isc-stork-server
$ sudo systemctl start isc-stork-server
```

To check the status:

```
$ sudo systemctl status isc-stork-server
```

Note: By default, the Stork server web service is exposed on port 8080 and can be tested using a web browser at <http://localhost:8080>. To use a different IP address or port, set the `STORK_REST_HOST` and `STORK_REST_PORT` variables in the `/etc/stork/stork.env` file.

The Stork server can be configured to run behind an HTTP reverse proxy using Nginx or Apache. The Stork server package contains an example configuration file for Nginx, in `/usr/share/stork/examples/nginx-stork.conf`.

The logging details, including colorization is configured analogously to the *Stork Agent logging settings*.

Stork can read and combine the configuration parameters from a few sources simultaneously. The command line flags have precedence over the environment variables read from the file when the `-use-env-file` flag is specified. The environment variables read from the file take precedence over the environment variables set in the current shell.

2.5.1.4 Stork UI Behind a Reverse Proxy

A reverse proxy is a server solution responsible for preliminary processing incoming requests from the Internet and redirecting them to specific web services running in the internal network. The reverse proxies may help increase performance (e.g., by caching responses), security (e.g., by enveloping the responses in TLS, logging the requests), and reliability (e.g., by allowing switching web service instances).

Stork is distributed with a basic configuration for Nginx. It is available, after installation from a package, in the `dist/server/usr/share/stork/examples/nginx-stork.conf` file. The same file is located in git repository: `etc/nginx-stork.conf`.

Stork Server can be configured to expose the web application from a URL subdirectory. It may be needed when there is no dedicated domain for Stork Server, and the web application is served from the subdirectory of an existing domain (e.g., `http://example.com/stork`).

If the backend executable (`stork-server`) and UI files (`/usr/share/stork/www` by default) are on the same machine, the backend is responsible for sharing the UI static files. You can configure the necessary subdirectory using the `--rest-base-url` CLI flag or the `STORK_REST_BASE_URL` environment variable. The value must be surrounded by slashes (e.g.: `/stork/`). The `--rest-base-url` CLI flag affects both the backend and UI. It changes the value of the `<base>` HTML tag in the `index.html` file (that modifies all links and URLs used by UI) and turns on the simple remapping of the requested URL (the backend trims the base path from processed URLs). The reverse proxy doesn't require any special configuration.

If the backend and the UI files are located on different machines, you must manually modify the value of the `<base>` HTML tag in the `index.html` file. The `href` attribute must be set to a necessary subdirectory. The value must be surrounded by slashes (e.g.: `/stork/`). Configure your HTTP proxy server to rewrite the requested URL and remove the base URL before passing the requests to Stork Server. Below is an example of configuring the `<VirtualHost>` section for Apache. See the `etc/httpd-stork.conf` file for full configuration.

```
<VirtualHost *:81>
  <LocationMatch "^/stork">
    RewriteEngine On
    RewriteCond %{REQUEST_URI} ^/stork/(.*)
    RewriteRule ^ /%1 [L]
  </LocationMatch>

  # Other location rules here...

</VirtualHost>
```

2.5.1.5 Securing the Database Connection

The PostgreSQL server can be configured to encrypt communications between the clients and the server. Detailed information on how to enable encryption on the database server, and how to create the suitable certificate and key files, is available in the [PostgreSQL documentation](#).

The Stork server supports secure communications with the database. The following configuration settings in the `server.env` file enable and configure communication encryption with the database server. They correspond with the SSL settings provided by `libpq` - the native PostgreSQL client library written in C:

- `STORK_DATABASE_SSLMODE` - the SSL mode for connecting to the database (i.e., `disable`, `require`, `verify-ca`, or `verify-full`); the default is `disable`
- `STORK_DATABASE_SSLCERT` - the location of the SSL certificate used by the server to connect to the database
- `STORK_DATABASE_SSLKEY` - the location of the SSL key used by the server to connect to the database
- `STORK_DATABASE_SSLROOTCERT` - the location of the root certificate file used to verify the database server's certificate

The default SSL mode setting, `disable`, configures the server to use unencrypted communication with the database. Other settings have the following meanings:

- `require` - use secure communication but do not verify the server's identity unless the root certificate location is specified and that certificate exists. If the root certificate exists, the behavior is the same as in the case of `verify-ca`.
- `verify-ca` - use secure communication and verify the server's identity by checking it against the root certificate stored on the Stork server machine.
- `verify-full` - use secure communication and verify the server's identity against the root certificate. In addition, check that the server hostname matches the name stored in the certificate.

Specifying the SSL certificate and key location is optional. If they are not specified, the Stork server uses the ones from the current user's home directory: `~/.postgresql/postgresql.crt` and `~/.postgresql/postgresql.key`. If they are not present, Stork tries to find suitable keys in common system locations.

Please consult the [libpq documentation](#) for similar `libpq` configuration details.

2.5.2 Installing the Stork Agent

There are two ways to install the packaged Stork agent on a monitored machine. The first method is to use the Cloudsmith repository, as with the Stork server installation. The second method, supported since Stork 0.15.0, is to use an installation script provided by the Stork server, which downloads the agent packages embedded in the server package. The preferred installation method depends on the selected agent registration type. Supported registration methods are described in *[Securing Connections Between the Stork Server and a Stork Agent](#)*.

2.5.2.1 Agent Configuration Settings

The following are the Stork agent configuration settings available in the `/etc/stork/agent.env` file after installing the package. All these settings use the `STORK_AGENT_` prefix to indicate that they configure the Stork agent. Configuring Stork using the environment variables is recommended for deployments using `systemd`.

Note: The environment file **IS NOT** read by default if you run the Stork agent manually (without using `systemd`). To load the environment variables from this file you should call the `. /etc/stork/agent.env` command before executing the binary (in the same shell instance) or run Stork with the `--use-env-file` switch.

The general settings:

- `STORK_AGENT_HOST` - the IP address of the network interface or DNS name which `stork-agent` should use to receive connections from the server; the default is `0.0.0.0` (i.e. listen on all interfaces)
- `STORK_AGENT_PORT` - the port number the agent should use to receive connections from the server; the default is `8080`
- `STORK_AGENT_LISTEN_STORK_ONLY` - this enables Stork functionality only, i.e. disables Prometheus exporters; the default is `false`
- `STORK_AGENT_LISTEN_PROMETHEUS_ONLY` - this enables the Prometheus exporters only, i.e. disables Stork functionality; the default is `false`
- `STORK_AGENT_SKIP_TLS_CERT_VERIFICATION` - this skips TLS certificate verification when `stork-agent` connects to Kea over TLS and Kea uses self-signed certificates; the default is `false`

The following settings are specific to the Prometheus exporters:

- `STORK_AGENT_PROMETHEUS_KEA_EXPORTER_ADDRESS` - the IP address or hostname the agent should use to receive the connections from Prometheus fetching Kea statistics; default is `0.0.0.0`
- `STORK_AGENT_PROMETHEUS_KEA_EXPORTER_PORT` - the port the agent should use to receive connections from Prometheus when fetching Kea statistics; the default is `9547`
- `STORK_AGENT_PROMETHEUS_KEA_EXPORTER_INTERVAL` - specifies how often the agent collects stats from Kea, in seconds; default is `10`
- `STORK_AGENT_PROMETHEUS_KEA_EXPORTER_PER_SUBNET_STATS` - enable or disable collecting per subnet stats from Kea; default is `true` (collecting enabled). You can use this option to limit the data passed to Prometheus/Grafana in large networks.
- `STORK_AGENT_PROMETHEUS_BIND9_EXPORTER_ADDRESS` - the IP address or hostname the agent should use to receive the connections from Prometheus fetching BIND9 statistics; default is `0.0.0.0` to listen on for incoming Prometheus connection; default is `0.0.0.0`
- `STORK_AGENT_PROMETHEUS_BIND9_EXPORTER_PORT` - the port the agent should use to receive the connections from Prometheus fetching BIND9 statistics; default is `9119`
- `STORK_AGENT_PROMETHEUS_BIND9_EXPORTER_INTERVAL` - specifies how often the agent collects stats from BIND9, in seconds; default is `10`

The last setting is used only when Stork agents register in the Stork server using an agent token:

- `STORK_AGENT_SERVER_URL` - the `stork-server` URL used by the agent to send REST commands to the server during agent registration

Warning: `stork-server` does not currently support communication with `stork-agent` via an IPv6 link-local address with zone ID (e.g., `fe80::%eth0`). This means that the `STORK_AGENT_HOST` variable must be set to a DNS name, an IPv4 address, or a non-link-local IPv6 address.

Stork can read and combine the configuration parameters from a few sources simultaneously. The command line flags have precedence over the environment variables read from the file when the `-use-env-file` flag is specified. The environment variables read from the file take precedence over the environment variables set in the current shell.

2.5.2.2 Logging Settings

Unless otherwise specified using `STORK_LOG_LEVEL`, the default value of `INFO` log level is used. Supported log levels are: `DEBUG`, `INFO`, `WARN`, `ERROR`.

To control the logging colorization, Stork supports the `CLICOLOR` and `CLICOLOR_FORCE` standard UNIX environment variables. When set, the following rules will be applied:

- **`CLICOLOR_FORCE != 0`**
ANSI colors should be enabled no matter what.
- **`CLICOLOR_FORCE == 0`**
Don't output ANSI color escape codes.
- **`CLICOLOR_FORCE` is unset and `CLICOLOR == 0`**
Don't output ANSI color escape codes.
- **Otherwise**
ANSI colors are enabled if TTY is used.

For example, to disable the output colorization:

```
rake run:agent CLICOLOR=0
```

Note: The `true` and `false` values are also accepted instead of the `1` and `0`.

2.5.2.3 Securing Connections Between the Stork Server and a Stork Agent

Connections between the server and the agents are secured using standard cryptography solutions, i.e. PKI and TLS.

The server generates the required keys and certificates during its first startup. They are used to establish safe, encrypted connections between the server and the agents with authentication at both ends of these connections. The agents use the keys and certificates generated by the server to create agent-side keys and certificates, during the agents' registration procedure described in the next sections. The private key and CSR certificate generated by an agent and signed by the server are used for authentication and connection encryption.

An agent can be registered in the server using one of the two supported methods:

1. using an agent token
2. using a server token

In the first case, an agent generates a token and passes it to the server requesting registration. The server associates the token with the particular agent. A Stork super administrator must approve the registration request in the web UI, ensuring that the token displayed in the UI matches the agent's token in the logs. The Stork agent is typically installed from the Cloudsmith repository when this registration method is used.

In the second registration method, a server generates a common token for all new registrations. The super admin must copy the token from the UI and paste it into the agent's terminal during the interactive agent registration procedure. This registration method does not require any additional approval of the agent's registration request in the web UI. If the pasted server token is correct, the agent should be authorized in the UI when the interactive registration completes. When this registration method is used, the Stork agent is typically installed using a script that downloads the agent packages embedded in the server.

The applicability of the two methods is described in [Registration Methods Summary](#).

The installation and registration processes using each method are described in the subsequent sections.

2.5.2.4 Securing Connections Between stork-agent and the Kea Control Agent

The Kea Control Agent (CA) may be configured to accept connections only over TLS. It requires specifying `trust-anchor`, `cert-file` and `key-file` values in the `kea-ctrl-agent.conf` file. For details, see the [Kea Administrator Reference Manual](#).

The Stork agent can communicate with Kea over TLS, via the same certificates that it uses in communication with the Stork server.

The Stork agent by default requires that the Kea Control Agent provide a trusted TLS certificate. If Kea uses a self-signed certificate, the Stork agent can be launched with the `--skip-tls-cert-verification` flag or `STORK_AGENT_SKIP_TLS_CERT_VERIFICATION` environment variable set to 1, to disable Kea certificate verification.

The Kea CA accepts only requests signed with a trusted certificate, when the `cert-required` parameter is set to `true` in the Kea CA configuration file. In this case, the Stork agent must use valid certificates; it cannot use self-signed certificates created during Stork agent registration.

Kea 1.9.0 added support for basic HTTP authentication to control access for incoming REST commands over HTTP. If the Kea CA is configured to use Basic Auth, valid credentials must be provided in the Stork agent credentials file: `/etc/stork/agent-credentials.json`.

By default, this file does not exist, but the `/etc/stork/agent-credentials.json.template` file provides example data. The template file can be renamed by removing the `.template` suffix; then the file can be edited and valid credentials can be provided. The `chown` and `chmod` commands should be used to set the proper permissions; this file contains the secrets, and should be readable/writable only by the user running the Stork agent and any administrators.

Warning: Basic HTTP authentication is weak on its own as there are known dictionary attacks, but those attacks require a “man in the middle” to get access to the HTTP traffic. That can be eliminated by using basic HTTP authentication exclusively over TLS. In fact, if possible, using client certificates for TLS is better than using basic HTTP authentication.

For example:

```
{
  "basic_auth": [
    {
      "ip": "127.0.0.1",
      "port": 8000,
      "user": "foo",
      "password": "bar"
    }
  ]
}
```

It contains a single object with a single “basic” key. The “basic” value is a list of the Basic Auth credentials. All credentials must contain the values for four keys:

- `ip` - the IPv4 or IPv6 address of the Kea CA. It supports IPv6 abbreviations (e.g. “FF:0000::” is the same as “ff::”).
- `port` - the Kea Control Agent port number.
- `user` - the Basic Auth user ID to use in connection with a specific Kea CA.
- `password` - the Basic Auth password to use in connection with a specific Kea CA.

To apply changes in the credentials file, the `stork-agent` daemon must be restarted.

If the credentials file is invalid, the Stork agent will run but without Basic Auth support. The notice will be indicated with a specific message in the log.

2.5.2.5 Installation From Cloudsmith and Registration With an Agent Token

This section describes how to install an agent from the Cloudsmith repository and perform the agent's registration using an agent token.

The Stork agent installation steps are similar to the Stork server installation steps described in *Installing on Debian/Ubuntu* and *Installing on CentOS/RHEL/Fedora*. Use one of the following commands depending on the local Linux distribution:

```
$ sudo apt install isc-stork-agent
```

```
$ sudo dnf install isc-stork-agent
```

instead of the server installation commands.

Next, specify the required settings in the `/etc/stork/agent.env` file. The `STORK_AGENT_SERVER_URL` should be the URL on which the server receives the REST connections, e.g. `http://stork-server.example.org:8080`. The `STORK_AGENT_HOST` should point to the agent's address (or name), e.g. `stork-agent.example.org`. Finally, a non-default agent port can be specified with the `STORK_AGENT_PORT`.

Note: Even though the examples provided in this documentation use the `http` scheme, we highly recommend using secure protocols in production environments. We use `http` in the examples because it usually makes it easier to start testing the software and eliminate all issues unrelated to the use of `https` before it is enabled.

Start the agent service:

```
$ sudo systemctl enable isc-stork-agent
$ sudo systemctl start isc-stork-agent
```

To check the status:

```
$ sudo systemctl status isc-stork-agent
```

The following log messages should be returned when the agent successfully sends the registration request to the server:

```
machine registered
stored agent signed cert and CA cert
registration completed successfully
```

A server administrator must approve the registration request via the web UI before a machine can be monitored. Visit the **Services -> Machines** page in the Stork UI, and click the **Unauthorized** button located above the list of machines on the right side. This list contains all machines pending registration approval. Before authorizing a machine, ensure that the agent token displayed on this list is the same as the agent token in the agent's logs or the `/var/lib/stork-agent/tokens/agent-token.txt` file. If they match, click on the **Action** button and select **Authorize**. The machine should now be visible on the list of authorized machines.

2.5.2.6 Installation With a Script and Registration With a Server Token

This section describes how to install an agent using a script and packages downloaded from the Stork server and register the agent using a server token.

To enable this installation, you must download Stork agent packages from cloudsmith.io for the operating systems on which the agents will be installed. Next, put the downloaded packages in the `assets/pkg` subdirectory of the directory holding Stork server's static UI content. It is defined by the `STORK_REST_STATIC_FILES_DIR` environment variable, and its default location is `/usr/share/stork/www`. The supported package types are DEB, RPM, and APK. The package file names must start with the `isc-stork-agent` prefix and end with the `.deb`, `.rpm`, or `.apk` extensions. It is recommended to leave the original filenames.

Open Stork in the web browser and log in as a user from the “super admin” group. Select **Services** and then **Machines** from the menu. Click on the **How to Install Agent on New Machine** button to display the agent installation instructions. Copy and paste the commands from the displayed window into the terminal on the machine where the agent is installed. These commands are also provided here for convenience:

```
$ wget http://stork.example.org:8080/stork-install-agent.sh
$ chmod a+x stork-install-agent.sh
$ sudo ./stork-install-agent.sh
```

`stork.example.org` is an example URL for the Stork server; it must be replaced with the real server URL used in the deployment.

The script downloads an OS-specific agent package from the Stork server (deb or RPM), installs the package, and starts the agent's registration procedure.

In the agent machine's terminal, a prompt for a server token is presented:

```
>>>> Server access token (optional):
```

The server token is available for a super admin user after clicking on the **How to Install Agent on New Machine** button in the **Services -> Machines** page. Copy the server token from the dialog box and paste it in at the prompt displayed on the agent machine.

The following prompt appears next:

```
>>>> IP address or FQDN of the host with Stork Agent (the Stork Server will use it to
↪connect to the Stork Agent):
```

Specify an IP address or fully qualified domain name (FQDN) that the server should use to reach out to an agent via the secure gRPC channel.

When asked for the port:

```
>>>> Port number that Stork Agent will use to listen on [8080]:
```

specify the port number for the gRPC connections, or hit Enter if the default port 8080 matches the local settings.

If the registration is successful, the following messages are displayed:

```
machine ping over TLS: OK
registration completed successfully
```

Unlike with *Installation From Cloudsmith and Registration With an Agent Token*, this registration method does not require approval via the web UI. The machine should already be listed among the authorized machines.

2.5.2.7 Installation With a Script and Registration With an Agent Token

This section describes how to install an agent using a script and packages downloaded from the Stork server and perform the agent's registration using an agent token. It is an interactive alternative to the procedure described in *Installation From Cloudsmith and Registration With an Agent Token*.

Start the interactive registration procedure following the steps in the *Installation With a Script and Registration With a Server Token* section.

In the agent machine's terminal, a prompt for a server token is presented:

```
>>>> Server access token (optional):
```

Because this registration method does not use the server token, do not type anything in this prompt. Hit Enter to move on.

The following prompt appears next:

```
>>>> IP address or FQDN of the host with Stork Agent (the Stork Server will use it to
↪connect to the Stork Agent):
```

Specify an IP address or FQDN that the server should use to reach out to an agent via the secure gRPC channel.

When asked for the port:

```
>>>> Port number that Stork Agent will use to listen on [8080]:
```

specify the port number for the gRPC connections, or hit Enter if the default port 8080 matches the local settings.

The following log messages should be returned when the agent successfully sends the registration request to the server:

```
machine registered
stored agent signed cert and CA cert
registration completed successfully
```

As with *Installation From Cloudsmith and Registration With an Agent Token*, the agent's registration request must be approved in the UI to start monitoring the newly registered machine.

2.5.2.8 Installation From Cloudsmith and Registration With a Server Token

This section describes how to install an agent from the Cloudsmith repository and perform the agent's registration using a server token. It is an alternative to the procedure described in *Installation With a Script and Registration With a Server Token*.

The Stork agent installation steps are similar to the Stork server installation steps described in *Installing on Debian/Ubuntu* and *Installing on CentOS/RHEL/Fedora*. Use one of the following commands, depending on the Linux distribution:

```
$ sudo apt install isc-stork-agent
```

```
$ sudo dnf install isc-stork-agent
```

Start the agent service:

```
$ sudo systemctl enable isc-stork-agent
$ sudo systemctl start isc-stork-agent
```


To check the status:

```
$ sudo systemctl status isc-stork-agent
```

Start the interactive registration procedure with the following command:

```
$ su stork-agent -s /bin/sh -c 'stork-agent register -u http://stork.example.org:8080'
```

The last parameter should be the appropriate Stork server URL.

Follow the same registration steps described in *Installation With a Script and Registration With a Server Token*.

2.5.2.9 Registration Methods Summary

Stork supports two different agent-registration methods, described above. Both methods can be used interchangeably, and it is often a matter of preference which one the administrator selects. However, the agent token registration may be more suitable in some situations. This method requires a server URL, agent address (or name), and agent port as registration settings. If they are known upfront, it is possible to prepare a system (or container) image with the agent offline. After starting the image, the agent sends the registration request to the server and awaits authorization in the web UI.

The agent registration with the server token is always manual. It requires copying the token from the web UI, logging into the agent, and pasting the token. Therefore, the registration using the server token is not appropriate when it is impossible or awkward to access the machine's terminal, e.g. in Docker. On the other hand, the registration using the server token is more straightforward because it does not require unauthorized agents' approval via the web UI.

If the server token leaks, it poses a risk that rogue agents might register. In that case, the administrator should regenerate the token to prevent the uncontrolled registration of new agents. Regeneration of the token does not affect already-registered agents. The new token must be used for any new registrations.

The server token can be regenerated in the **How to Install Agent on New Machine** dialog box available after navigating to the **Services -> Machines** page.

2.5.2.10 Agent Setup Summary

After successful agent setup, the agent periodically tries to detect installed Kea DHCP or BIND9 services on the system. If it finds them, they are reported to the Stork server when it connects to the agent.

Further configuration and usage of the Stork server and the Stork agent are described in the *Using Stork* chapter.

2.5.2.11 Inspecting Keys and Certificates

The Stork server maintains TLS keys and certificates internally to secure the communication between **stork-server** and any agents. They can be inspected and exported using **stork-tool**, with a command such as:

```
$ stork-tool cert-export --db-url postgresql://user:pass@localhost/dbname -f srvcert -o
↪srv-cert.pem
```

The above command may fail if the database password contains any characters requiring URL encoding. In this case, a command line with multiple switches can be used instead:

```
$ stork-tool cert-export --db-user user --db-password pass --db-host localhost --db-name
↪dbname -f srvcert -o srv-cert.pem
```

The certificates and secret keys can be inspected using OpenSSL, using commands such as `openssl x509 -noout -text -in srv-cert.pem` (for the certificates) and `openssl ec -noout -text -in cakey` (for the keys).

There are five secrets that can be exported or imported: the Certificate Authority secret key (`cakey`), the Certificate Authority certificate (`cacert`), the Stork server private key (`srvkey`), the Stork server certificate (`svrcert`), and a server token (`srvtkn`).

For more details, please see *stork-tool - A Tool for Managing Stork Server*.

2.5.2.12 Using External Keys and Certificates

It is possible to use external TLS keys and certificates. They can be imported to the Stork server using `stork-tool`:

```
$ stork-tool cert-import --db-url postgresql://user:pass@localhost/dbname -f svrcert -i ↵
↵srv-cert.pem
```

The above command may fail if the database password contains any characters requiring URL encoding. In this case, a command line with multiple switches can be used instead:

```
$ stork-tool cert-import --db-user user --db-password pass --db-host localhost --db-name ↵
↵dbname -f svrcert -i srv-cert.pem
```

Both the Certificate Authority key and the Certificate Authority certificate must be changed at the same time, as the certificate depends on the key. If they are changed, then the server key and certificate must also be changed.

Note: Imported certificates and keys must follow the same standards as those self-generated by the Stork server. They must also have the same format. This [ISC Knowledge Base article](#) provides step-by-step examples of generating a new set of certificates using OpenSSL and importing them to Stork. Note that the example OpenSSL configurations from this article may have to be adjusted to the specifics of your deployment.

For more details, please see *stork-tool - A Tool for Managing Stork Server*.

2.5.3 Installing the hooks

The hook is an additional file (plugin) that extends the standard Stork functionalities. It contains functions that are called during handling of various operations and can change the typical flow or run in parallel. Independent developers may create the hooks and enhance the Stork applications with new, optional features.

The hook packages are distributed as RPM and DEB packages on Cloudsmith.

The hooks are binary files with the `.so` extension. These files must be placed in the hook directory. The default location is `/var/lib/stork-agent/hooks` for Stork agent and `/var/lib/stork-server/hooks` for Stork server. You can change it using the `--hook-directory` CLI option or setting the `STORK_AGENT_HOOK_DIRECTORY` or `STORK_SERVER_HOOK_DIRECTORY` environment variable.

All the hooks must be compatible with the used Stork application (agent or server) and its exact version. If the hook directory contains non-hook files or out-of-date hooks, then Stork will not run.

The hooks may provide own configuration options. The list of available options is listed in the output of the `stork-agent --help` and `stork-server --help` commands.

The list of supported Stork server hooks:

- LDAP authentication

The hook provides the possibility to authenticate users by LDAP credentials, fetch their profiles, and map LDAP groups into Stork roles.

2.5.4 Upgrading

Due to the new security model introduced with TLS in Stork 0.15.0, upgrades from versions 0.14.0 and earlier require the agents to be re-registered.

The server upgrade procedure is the same as the initial installation procedure.

Install the new packages on the server. Installation scripts in the deb/RPM package will perform the required database and other migrations.

2.6 Installing From Sources

2.6.1 Compilation Prerequisites

Usually, it is more convenient to install Stork using native packages. See *Supported Systems* and *Installing From Packages* for details regarding supported systems. However, the sources can also be built separately.

The dependencies that need to be installed to build the Stork sources are:

- Rake
- Java Runtime Environment (only if building natively, not using Docker)
- Docker (only if running in containers; this is needed to build the demo)

Other dependencies are installed automatically in a local directory by Rake tasks, which does not require root privileges. If the demo environment will be run, Docker is needed but not Java; Docker installs Java within a container.

For details about the environment, please see the Stork wiki at <https://gitlab.isc.org/isc-projects/stork/-/wikis/Install>.

2.6.2 Download Sources

The Stork sources are available in ISC's GitLab instance: <https://gitlab.isc.org/isc-projects/stork>.

To get the latest sources invoke:

```
$ git clone https://gitlab.isc.org/isc-projects/stork
```

2.6.3 Building

There are two Stork components:

- **stork-agent** - this is a binary, written in Go
- **stork-server** - this is comprised of two parts: - backend service - a binary, written in Go - frontend - an Angular application written in Typescript

All components can be built using the following command:

```
$ rake build
```

The agent component is installed using this command:

```
$ rake install:agent
```

and the server component with this command:

```
$ rake install:server
```

By default, all components are installed in the specific system directories; this is useful for installation in a production environment. For the testing purposes it can be customized via the `DEST` variable, e.g.:

```
$ rake install:server DEST=/home/user/stork
```

2.6.4 Installing on FreeBSD

Stork is not regularly tested on FreeBSD but can be installed on this operating system with the manual steps provided below.

The first step is the installation of packages from the repository:

```
pkg install ruby
pkg install rubygem-rake
pkg install wget
pkg install openjdk11-jre
pkg install node14
pkg install npm-node14
npm install -g npm
pkg install python3
pkg install protobuf
pkg install gcc
pkg install gtar
```

The utility to build the packages requires the GNU tar in `PATH`. The BSD tar isn't compatible. We need to rename the existing executable.

```
mv /usr/bin/tar /usr/bin/bsdtar
ln -s /usr/local/bin/gtar /usr/bin/tar
```

Stork build system can install all remaining dependencies automatically.

The binary packages can be built using:

```
rake build:server_pkg
rake build:agent_pkg
```

The output binaries will be located in the `dist/pkgs/` directory and can be installed using the `pkg install` command.

2.6.5 Installing on OpenBSD

Stork is not regularly tested on OpenBSD but can be installed on this operating system with the manual steps provided below. The installation guide is similar to FreeBSD one.

The first step is the installation of packages from the repository:

```
pkg_add ruby
ln -s /usr/local/bin/gem31 /usr/local/bin/gem
gem install --user-install rake
pkg_add wget
pkg_add jdk
pkg_add node
pkg_add unzip
pkg_add protobuf
pkg_add gcc
pkg_add go
```

Stork requires Golang version 1.18 or later.

Stork build system can install all remaining dependencies automatically.

Unfortunately, there is no possibility to build the binary packages for OpenBSD. But it is possible to build the contents of the packages (executables, UI, man, and docs).

```
rake build:server_dist
rake build:agent_dist
```

The output files will be located in the `dist/` directory.

2.6.6 Cross-compilation

Warning: Our tests do not cover the cross-compilation feature; **you use it at your own risk.**

The Stork build system fully supports Linux and MacOS operating systems on the AMD64 and ARM64 architectures. It is also prepared to handle FreeBSD and OpenBSD with some limitations but support for these systems isn't actively maintained.

The Stork agent, server, and tool are written in pure Golang, which means they can be easily cross-compiled on all supported platforms.

You can use the `rake utils:list_go_supported_platforms` to get a list of all supported operating systems and architectures.

To build any Stork component for a specific platform, you need to provide the `STORK_GOOS` (for the operating system), `STORK_GOARCH` (for the architecture) and (optionally) `STORK_GOARM` (for ARM version, ARM architectures only) environment variables:

```
rake build:server STORK_GOOS=darwin STORK_GOARCH=arm64 STORK_GOARM=8
rake build:agent STORK_GOOS=freebsd STORK_GOARCH=amd64
```

These variables are supported for the `build:server`, `build:agent`, `build:agent` commands to compile the executable binaries. They can also be used with combination of the `build:server_pkg` and `build:agent_pkg` commands to build the packages:

```
rake build:server_pkg STORK_GOOS=darwin STORK_GOARCH=arm64
rake build:agent_pkg STORK_GOOS=freebsd STORK_GOARCH=amd64
```

Warning: Remember that the output package type always depends on the current operating system, not the executable type. It means that specifying the darwin operating system in STORK_GOOS and building the package on Debian causes generating a DEB package with a macOS-compatible executable, which is useless.

It is not recommended to compile Stork for 32-bit architectures as it may cause problems with unexpected integer overflows. Stork was never designed to operate on non-posix platforms, so Windows is not and will not be supported. Compiling Stork components for Windows is discouraged because Golang's standard library may suppress some errors related to the file operations on the NTFS filesystem.

2.7 Integration With Prometheus and Grafana

Stork can optionally be integrated with [Prometheus](#), an open source monitoring and alerting toolkit, and [Grafana](#), an easy-to-view analytics platform for querying, visualization, and alerting. Grafana requires external data storage. Prometheus is currently the only environment supported by both Stork and Grafana. It is possible to use Prometheus without Grafana, but using Grafana requires Prometheus.

2.7.1 Prometheus Integration

The Stork agent, by default, makes Kea statistics, as well as some BIND 9 statistics, available in a format understandable by Prometheus. In Prometheus nomenclature, the Stork Agent works as a Prometheus “exporter.” If the Prometheus server is available, it can be configured to monitor Stork agents. To enable stork-agent monitoring, the `prometheus.yml` file (which is typically stored in `/etc/prometheus/`, but this may vary depending on the installation) must be edited to add the following entries:

```
# statistics from Kea
- job_name: 'kea'
  static_configs:
    - targets: ['agent-kea.example.org:9547', 'agent-kea6.example.org:9547', ... ]

# statistics from bind9
- job_name: 'bind9'
  static_configs:
    - targets: ['agent-bind9.example.org:9119', 'another-bind9.example.org:9119', ... ]
```

By default, the Stork agent exports Kea data on TCP port 9547 and BIND 9 data on TCP port 9119. This can be configured using command-line parameters, or the Prometheus export can be disabled altogether. For details, see the Stork agent manual page at *stork-agent - Stork Agent to Monitor BIND 9 and Kea services*.

The Stork server can also be optionally integrated, but Prometheus support for it is disabled by default. To enable it, run the server with the `-m` or `--metrics` flag or set the `STORK_SERVER_ENABLE_METRICS` environment variable. Next, update the `prometheus.yml` file:

```
# statistics from Stork Server
- job_name: 'storkserver'
  static_configs:
    - targets: ['server.example.org:8080']
```

The Stork server exports metrics on the assigned HTTP/HTTPS port (defined via the `--rest-port` flag).

Note: The Prometheus client periodically collects metrics from the clients (`stork-server` or `stork-agent`, for example), via an HTTP call. By convention, the endpoint that shares the metrics has the `/metrics` path. This endpoint returns data in Prometheus-specific format.

Warning: The Prometheus `/metrics` endpoint does not require authentication. Therefore, securing this endpoint from external access is highly recommended to prevent unauthorized parties from gathering the server's metrics. One way to restrict endpoint access is by using an appropriate HTTP proxy configuration to allow only local access or access from the Prometheus host. Please consult the NGINX example configuration file shipped with Stork.

After restarting, the Prometheus web interface can be used to inspect whether the statistics have been exported properly. Kea statistics use the `kea_` prefix (e.g. `kea_dhcp4_addresses_assigned_total`); BIND 9 statistics will eventually use the `bind_` prefix (e.g. `bind_incoming_queries_tcp`); and Stork server statistics use the `storkserver_` prefix.

2.7.2 Alerting in Prometheus

Prometheus provides the ability to configure alerting. A good starting point is the [Prometheus documentation on alerting](#). Briefly, the three main steps are: configure the Alertmanager; configure Prometheus to talk to the Alertmanager; and define the alerting rules in Prometheus. There are no specific requirements or recommendations, as these are very deployment-dependent. The following is an incomplete list of ideas that could be considered:

- The `storkserver_auth_unreachable_machine_total` metric is reported by `stork-server` and shows the number of unreachable machines. Its value under normal circumstances should be zero. Configuring an alert for non-zero values may be the best indicator of a large-scale problem, such as a whole VM or server becoming unavailable.
- The `storkserver_auth_authorized_machine_total` and `storkserver_auth_unauthorized_machine_total` metrics may be used to monitor situations when new machines (e.g. by automated VM cloning) may appear in the network or existing machines may disappear.
- The `kea_dhcp4_addresses_assigned_total` metric, along with `kea_dhcp4_addresses_total`, can be used to calculate pool utilization. If the server allocates all available addresses, it will not be able to handle new devices, which is one of the most common failure cases of the DHCPv4 server. Depending on the deployment specifics, a threshold alert when the pool utilization approaches 100% should be seriously considered.
- Contrary to popular belief, DHCPv6 can also run out of resources, in particular with prefix delegation (PD). The `kea_dhcp6_pd_assigned_total` metric divided by `kea_dhcp6_pd_total` can be considered an indicator of PD pool utilization. It is an important metric if PD is being used.

The alerting mechanism configured in Prometheus has the relative advantage of not requiring an additional component (Grafana). The alerting rules are defined in a text file using simple YAML syntax. For details, see the [Prometheus documentation on alerting rules](#). One potentially important feature is Prometheus' ability to automatically discover available Alertmanager instances, which may be helpful in various redundancy considerations. The Alertmanager provides a rich list of receivers, which are the actual notification mechanisms used: email, PagerDuty, Pushover, Slack, Opsgenie, webhook, WeChat, and more.

ISC makes no specific recommendations between Prometheus or Grafana. This is a deployment consideration.

2.7.3 Grafana Integration

Stork provides several Grafana templates that can easily be imported, available in the `grafana/` directory of the Stork source code. The currently available templates are `bind9-resolver.json`, `kea-dhcp4.json`, and `kea-dhcp6.json`. Grafana integration requires three steps:

1. Prometheus must be added as a data source. This can be done in several ways, including using the user interface to edit the Grafana configuration files. This is the easiest method; for details, see the Grafana documentation about Prometheus integration. Using the Grafana user interface, select Configuration, select Data Sources, click “Add data source,” and choose Prometheus; then specify the necessary parameters to connect to the Prometheus instance. In test environments, the only necessary parameter is the URL, but authentication is also desirable in most production deployments.
2. Import the existing dashboard. In the Grafana UI, click Dashboards, then Manage, then Import, and select one of the templates, e.g. `kea-dhcp4.json`. Make sure to select the Prometheus data source added in the previous step. Once imported, the dashboard can be tweaked as needed.
3. Once Grafana is configured, go to the Stork user interface, log in as “super admin”, click Settings in the Configuration menu, and then add the URLs for Grafana and Prometheus that point to the installations. Once this is done, Stork will be able to show links for subnets leading to specific subnets.

Alternatively, a Prometheus data source can be added by editing `datasource.yaml` (typically stored in `/etc/grafana/`, but this may vary depending on the installation) and adding entries similar to this one:

```
datasources:
- name: Stork-Prometheus instance
  type: prometheus
  access: proxy
  url: http://prometheus.example.org:9090
  isDefault: true
  editable: false
```

The Grafana dashboard files can also be copied to `/var/lib/grafana/dashboards/` (again, the exact location may vary depending on the installation).

Example dashboards with some live data can be seen in the [Stork screenshots gallery](#).

2.7.4 Subnet Identification

The Kea Control Agent shares subnet statistics labeled with the internal Kea IDs. The Prometheus/Grafana subnet labels depend on the installed Kea hooks. By default, the internal, numeric Kea IDs are used. However, if the `subnet_cmds` hook is installed, then the numeric IDs are resolved to subnet prefixes. This makes the Grafana dashboard more human-friendly and descriptive.

2.7.5 Alerting in Grafana

Grafana offers multiple alerting mechanism options that can be used with Stork; users are encouraged to see the [Grafana page on alerting](#).

The list of notification channels (i.e. the delivery mechanisms) is extensive, as it supports email, webhook, Prometheus’ Alertmanager, PagerDuty, Slack, Telegram, Discord, Google Hangouts, Kafka REST Proxy, Microsoft Teams, Opsgenie, Pushover, and more. Existing dashboards provided by Stork can be modified and new dashboards can be created. Grafana first requires a notification channel to be configured (Alerting -> Notifications Channel menu). Once configured, existing panels can be edited with alert rules. One caveat is that most panels in the Stork dashboards use

template variables, which are not supported in alerting. This [stackoverflow thread](#) discusses several ways to overcome this limitation.

Compared to Prometheus alerting, Grafana alerting is a bit more user-friendly. The alerts are set using a web interface, with a flexible approach that allows custom notification messages, such as instructions on what to do when receiving an alert, information on how to treat situations where received data is null or there is a timeout, etc.

The defined alerts are considered an integral part of a dashboard. This may be a factor in a deployment configuration, e.g. the dashboard can be tweaked to specific needs and then deployed to multiple sites.

USING STORK

This section describes how to use the features available in Stork. To connect to Stork, use a web browser and connect to port 8080 on the Stork server machine. If `stork-server` is running on a localhost, it can be reached by navigating to <http://localhost:8080>.

3.1 Managing Users

A default administrator account is created when Stork is initially installed. It can be used to sign in to the system via the web UI, with the username `admin` and password `admin`.

To see a list of existing users, click on the **Configuration** menu and choose **Users**. There will be at least one user, `admin`.

To add a new user, click **Create User Account**. A new tab opens to specify the new account parameters. Some fields have specific restrictions:

- The **username** can consist of only letters, numbers, and an underscore (`_`).
- The **e-mail** field is optional, but if specified, it must be a well-formed e-mail address.
- The **firstname** and **lastname** fields are mandatory for the user accounts managed by Stork. They are optional for authentication methods provided by hooks.
- The **password** must only contain letters, digits, `@`, `.`, `!`, `+`, or `-`, and must be at least eight characters long.

Currently, each user is associated with one of the two predefined groups (roles), which are `super-admin` or `admin`; one of these must be selected when a user account is created. Both types of users can view Stork status screens, edit interval and reporting configuration settings, and add/remove machines for monitoring. `super-admin` users can also create and manage user accounts.

Once the new user account information has been specified and all requirements are met, the **Save** button becomes active and the new account can be enabled.

3.2 Changing a User Password

An initial password is assigned by the administrator when a user account is created. Each user should change their password when first logging into the system. To change the password, click on the **Profile** menu and choose **Settings** to display the user profile information. Click on **Change password** in the menu bar on the left and specify the current password in the first input box. The new password must be entered and confirmed in the second and third input boxes, and must meet the password requirements specified in the previous section. When all entered data is valid, the **Save** button is activated to change the password.

3.3 Configuration Settings

It is possible to control some of the Stork configuration settings from the web interface. Click on the **Configuration** menu and choose **Settings**. There are two classes of settings available: **Intervals** and **Grafana & Prometheus**.

Intervals settings specify the configuration of “pullers.” A puller is a mechanism in Stork which triggers a specific action at the specified interval. Each puller has its own specific action and interval. The puller interval is specified in seconds and designates a time period between the completion of the previously invoked action and the beginning of the next invocation of this action. For example, if the Kea Hosts Puller Interval is set to 10 seconds and it takes five seconds to pull the hosts information, the time period between the starts of the two consecutive attempts to pull the hosts information is 15 seconds.

The pull time varies between deployments and depends on the amount of information pulled, network congestion, and other factors. The interval setting guarantees that there is a constant idle time between any consecutive attempts.

The **Grafana & Prometheus** settings currently allow the URLs of the Prometheus and Grafana instances used with Stork to be specified.

3.4 Connecting and Monitoring Machines

3.4.1 Monitoring a Machine

Monitoring of registered machines is accomplished via the **Services** menu, under **Machines**. A list of currently registered machines is displayed, with multiple pages available if needed.

A filtering mechanism that acts as an omnibox is available. Via a typed string, Stork can search for an address, agent version, hostname, OS, platform, OS version, kernel version, kernel architecture, virtualization system, or host ID field.

The state of a machine can be inspected by clicking its hostname; a new tab opens with the machine’s details. Multiple tabs can be open at the same time, and clicking **Refresh** updates the available information.

The machine state can also be refreshed via the **Action** menu. On the **Machines** list, each machine has its own menu; click on the triple-lines button at the right side and choose the **Refresh** option.

3.4.2 Disconnecting From a Machine

To stop monitoring a machine, go to the **Machines** list, find the machine to stop monitoring, click on the triple-lines button at the right side, and choose **Delete**. This terminates the connection between the Stork server and the agent running on the machine, and the server will no longer monitor that machine; however, the **stork-agent** process will continue running. Complete shutdown of a **stork-agent** process must be done manually, e.g. by connecting to the machine using **ssh** and stopping the agent there. For example, when the Stork Agent has been installed from packages, run:

```
$ sudo systemctl stop isc-stork-agent
```

Alternatively:

```
$ sudo killall -9 stork-agent
```

3.4.3 Dumping Diagnostic Information Into a File

It is sometimes difficult or impossible to diagnose issues without seeing the actual logs, database contents, and configuration files. Gathering such information can be challenging for a user because it requires looking into many places like databases, remote machine logs, etc.

Stork makes it convenient for users to gather diagnostic information from the selected machines with a single click. Navigate to the **Machines** page (i.e., the page where all monitored machines are listed), click on the **Action** button for the selected machine, and choose the **Dump Troubleshooting Data** option. Alternatively, navigate to the selected machine's page and click on the **Dump Troubleshooting Data** button at the bottom of the page. In both cases, the Stork server will automatically gather useful diagnostics information and offer it for download as a `tar.gz` file. The downloaded package contains configurations, log tails, `stork-server` settings, warning and error-level events, high availability services' states etc.

Note: Stork sanitizes passwords and other sensitive information when it creates the package.

The tarball can be easily sent via email or attached to a bug report.

3.5 Monitoring Applications

3.5.1 Application Status

Kea DHCP applications discovered on connected machines are listed via the top-level menu bar, under **Services**. The list view includes the application version, application status, and some machine details. The **Action** button is also available, to refresh the information about the application.

The application status displays a list of daemons belonging to the application. Several daemons may be presented in the application status columns; typically, they include: DHCPv4, DHCPv6, DDNS, and Kea Control Agent (CA).

Stork uses `rndc` to retrieve the application's status. It looks for the `controls` statement in the configuration file, and uses the first listed control point for monitoring the application.

Furthermore, the Stork agent can be used as a Prometheus exporter if `named` is built with `json-c`, because it gathers statistics via the JSON statistics API. The `named.conf` file must have `statistics-channel` configured; the exporter queries the first listed channel. Stork is able to export the most metrics if `zone-statistics` is set to `full` in the `named.conf` configuration.

For Kea, the listed daemons are those that Stork finds in the Control Agent (CA) configuration file. A warning sign is displayed for any daemons from the CA configuration file that are not running. When the Kea installation is simply using the default CA configuration file, which includes configuration of daemons that are never intended to be launched, it is recommended to remove (or comment out) those configurations to eliminate unwanted warnings from Stork about inactive daemons.

3.5.2 Friendly App Names

Every app connected to Stork is assigned a default name. For example, if a Kea app runs on the machine `abc.example.org`, this app's default name is `kea@abc.example.org`. Similarly, if a BIND 9 app runs on the machine with the address `192.0.2.3`, the resulting app name is `bind9@192.0.2.3`. If multiple apps of a given type run on the same machine, a postfix with a unique identifier is appended to the duplicated names, e.g. `bind9@192.0.2.3%56`.

The default app names are unique so that the user can distinguish them in the dashboard, apps list, events panel, and other views. However, the default names may become lengthy when machines names consist of fully qualified domain names. When machines' IP addresses are used instead of FQDNs, the app names are less meaningful for someone not familiar with addressing in the managed network. In these cases, users may prefer replacing the default app names with more descriptive ones.

Suppose there are two DHCP servers in the network, one on the first floor of a building and one on the second floor. A user may assign the names `Floor 1 DHCP` and `Floor 2 DHCP` to the respective DHCP servers in this case. The new names need not have the same pattern as the default names and may contain whitespace. The `@` character is not required, but if it is present, the part of the name following this character (and before an optional `%` character) must be an address or name of the machine monitored in Stork. The following names: `dhcp-server@floor1%123` and `dhcp-server@floor1`, are invalid unless `floor1` is a monitored machine's name. The special notation using two consecutive `@` characters can be used to suppress this check. The `dhcp-server@@floor1` is a valid name even if `floor1` is not a machine's name. In this case, `floor1` can be a physical location of the DHCP server in a building.

To modify an app's name, navigate to the selected app's view. For example, select `Services` from the top menu bar and then click `Kea Apps`. Select an app from the presented apps list. Locate and click the pencil icon next to the app name in the app view. In the displayed dialog box, type the new app name. If the specified name is valid, the `Rename` button is enabled. Click this button to submit the new name. The `Rename` button is disabled if the name is invalid. In this case, a hint is displayed to explain the issues with the new name.

3.5.3 IPv4 and IPv6 Subnets per Kea Application

One of the primary configuration aspects of any network is the layout of IP addressing. This is represented in Kea with IPv4 and IPv6 subnets. Each subnet represents addresses used on a physical link. Typically, certain parts of each subnet ("pools") are delegated to the DHCP server to manage. Stork is able to display this information.

One way to inspect the subnets and pools within Kea is by looking at each Kea application to get an overview of what configurations a specific Kea application is serving. A list of configured subnets on that specific Kea application is displayed. The following picture shows a simple view of the Kea DHCPv6 server running with a single subnet, with three pools configured in it.

Kea App 2 Refresh App

Machine: agent-kea6

DHCPv6 CA

Overview

- Version: 1.7.4
- Version Ext: 1.7.4
- tarball
- linked with: log4cplus 1.1.2, OpenSSL 1.1.1 11 Sep 2018
- database: MySQL backend 9.1, library 5.7.29, PostgreSQL backend 6.0, library 100010
- Memfile backend 2.1
- Hooks: no hooks
- Uptime: 30 minutes 38 seconds
- Last Reloaded At: 2020-02-05 11:20:45

Subnet ID	Subnet	Pools
1	2001:db8:1::64	2001:db8:1:0:1::/80, 2001:db8:1:0:2::/80, 2001:db8:1:0:3::/80

1 of 1 pages « 1 » 10

3.5.4 IPv4 and IPv6 Subnets in the Whole Network

It is convenient to see the complete overview of all subnets configured in the network that are being monitored by Stork. Once at least one machine with the Kea application running is added to Stork, click on the DHCP menu and choose Subnets to see all available subnets. The view shows all IPv4 and IPv6 subnets, with the address pools and links to the applications that are providing them. An example view of all subnets in the network is presented in the figure below.

DHCP Subnets

Q Filter subnets: Protocol:

Subnet ID	Subnet	Pools	App ID
1	192.0.2.0/24	192.0.2.1-192.0.2.50 192.0.2.51-192.0.2.100 192.0.2.101-192.0.2.150 192.0.2.151-192.0.2.200	3
1	192.0.3.0/24	192.0.3.1-192.0.3.200	4
1	192.0.3.0/24	192.0.3.1-192.0.3.200	5
1	2001:db8:1::/64	2001:db8:1:0:1::/80 2001:db8:1:0:2::/80 2001:db8:1:0:3::/80	2

1 of 1 pages

Stork provides filtering capabilities; it is possible to choose whether to see IPv4 only, IPv6 only, or both. There is also an omniseach box available where users can type a search string. For strings of four characters or more, the filtering takes place automatically, while shorter strings require the user to hit Enter. For example, in the above example it is possible to show only the first (192.0.2.0/24) subnet by searching for the *0.2* string. One can also search for specific pools, and easily filter the subnet with a specific pool, by searching for part of the pool range, e.g. *3.200*.

Stork displays pool utilization for each subnet, with the absolute number of addresses allocated and usage percentage. There are two thresholds: 80% (warning; the pool utilization bar turns orange) and 90% (critical; the pool utilization bar turns red).

3.5.5 IPv4 and IPv6 Networks

Kea uses the concept of a shared network, which is essentially a stack of subnets deployed on the same physical link. Stork retrieves information about shared networks and aggregates it across all configured Kea servers. The **Shared Networks** view allows the inspection of networks and the subnets that belong in them. Pool utilization is shown for each subnet.

3.5.6 Host Reservations

3.5.6.1 Listing Host Reservations

Kea DHCP servers can be configured to assign static resources or parameters to the DHCP clients communicating with the servers. Most commonly these resources are the IP addresses or delegated prefixes. However, Kea also allows assignment of hostnames, PXE boot parameters, client classes, DHCP options, and other parameters. The mechanism by which a given set of resources and/or parameters is associated with a given DHCP client is called “host reservations.”

A host reservation consists of one or more DHCP identifiers used to associate the reservation with a client, e.g. MAC address, DUID, or client identifier; and a collection of resources and/or parameters to be returned to the client if the client’s DHCP message is associated with the host reservation by one of the identifiers. Stork can detect existing host reservations specified both in the configuration files of the monitored Kea servers and in the host database backends accessed via the Kea Host Commands premium hook library.

All reservations detected by Stork can be listed by selecting the DHCP menu option and then selecting **Host Reservations**.

The first column in the presented view displays one or more DHCP identifiers for each host in the format `hw-address=0a:1b:bd:43:5f:99`, where `hw-address` is the identifier type. In this case, the identifier type is the MAC address of the DHCP client for which the reservation has been specified. Supported identifier types are described

in the following sections of the Kea Administrator Reference Manual (ARM): [Host Reservation in DHCPv4](#) and [Host Reservation in DHCPv6](#).

The next two columns contain the static assignments of the IP addresses and/or delegated prefixes to the clients. There may be one or more such IP reservations for each host.

The **Hostname** column contains an optional hostname reservation, i.e., the hostname assigned to the particular client by the DHCP servers via the **Hostname** or **Client FQDN** option.

The **Global/Subnet** column contains the prefixes of the subnets to which the reserved IP addresses and prefixes belong. If the reservation is global, i.e., is valid for all configured subnets of the given server, the word “global” is shown instead of the subnet prefix.

Finally, the **App Name** column includes one or more links to Kea applications configured to assign each reservation to the client. The number of applications is typically greater than one when Kea servers operate in the High Availability setup. In this case, each of the HA peers uses the same configuration and may allocate IP addresses and delegated prefixes to the same set of clients, including static assignments via host reservations. If HA peers are configured correctly, the reservations they share will have two links in the **App Name** column. Next to each link there is a label indicating whether the host reservation for the given server has been specified in its configuration file or a host database (via the **Host Commands** premium hook library).

The **Filter hosts** input box is located above the **Hosts** table. It allows the hosts to be filtered by identifier types, identifier values, IP reservations, and hostnames, and by globality, i.e., `is:global` and `not:global`. When filtering by DHCP identifier values, it is not necessary to use colons between the pairs of hexadecimal digits. For example, the reservation `hw-address=0a:1b:bd:43:5f:99` will be found whether the filtering text is `1b:bd:43` or `1bdd43`.

The filtering mechanism also recognizes a set of keywords that can be used in combination with integer values to search host reservations by selected properties. For example, type:

- `appId:2` to search the host reservations belonging to the app with ID 2.
- `subnetId:78` to search the host reservations in subnet with ID 78. In this case the ID is the one assigned to the subnet by Stork.
- `keaSubnetId:123` to search the host reservations in subnets with ID 123 assigned in the Kea configurations.

3.5.6.2 Host Reservation Usage Status

Clicking on a selected host in the host reservations list opens a new tab that shows host details. The tab also includes information about reserved addresses and delegated prefixes usage. Stork needs to query Kea servers to gather the lease information for each address and prefix in the selected reservation. It may take several seconds or longer before this information is available. The lease information can be refreshed using the **Leases** button at the bottom of the tab.

The usage status is shown next to each IP address and delegated prefix. Possible statuses and their meanings are listed in the table below.

Table 1: Possible IP reservation statuses

Status	Meaning
in use	There are valid leases assigned to the client. The client owns the reservation, or the reservation includes the <code>flex-id</code> or <code>circuit-id</code> identifier, making it impossible to detect conflicts (see note below).
expired	At least one of the leases assigned to the client owning the reservation is expired.
declined	The address is declined on at least one of the Kea servers.
in conflict	At least one of the leases for the given reservation is assigned to a client that does not own this reservation.
unused	There are no leases for the given reservation.

View status details by expanding a selected address or delegated prefix row. Clicking on the selected address or delegated prefix navigates to the leases search page, where all leases associated with the address or prefix can be listed.

Note: Detecting `in conflict` status is currently not supported for host reservations with `flex-id` or `circuit-id` identifiers. If there are valid leases for such reservations, they are marked `in use` regardless of whether the conflict exists.

3.5.6.3 Sources of Host Reservations

There are two ways to configure Kea servers to use host reservations. First, the host reservations can be specified within the Kea configuration files; see [Host Reservation in DHCPv4](#) for details. The other way is to use a host database backend, as described in [Storing Host Reservations in MySQL or PostgreSQL](#). The second solution requires the given Kea server to be configured to use the `host_cmds` premium hook library. This library implements control commands used to store and fetch the host reservations from the host database to which the Kea server is connected. If the `host_cmds` hook library is not loaded, Stork only presents the reservations specified within the Kea configuration files.

Stork periodically fetches the reservations from the host database backends and updates them in the local database. The default interval at which Stork refreshes host reservation information is set to 60 seconds. This means that an update in the host reservation database is not visible in Stork until up to 60 seconds after it was applied. This interval is configurable in the Stork interface.

Note: The list of host reservations must be manually refreshed by reloading the browser page to see the most recent updates fetched from the Kea servers.

3.5.6.4 Creating Host Reservations

Above the list of the host reservations, there is the **New Host** button that opens a tab where you can specify a new host reservation in one or more Kea servers. These Kea servers must be configured to use the `host_cmds` hooks library, and only these servers are available for selection in the **DHCP Servers** dropdown.

You have a choice between a subnet-level or global host reservation. Selecting a subnet using the **Subnet** dropdown is required for a subnet-level reservation. If the desired subnet is not displayed in the dropdown, it is possible that the selected DHCP servers do not include this subnet in their configuration. Setting the **Global reservation** option disables subnet selection.

To associate the new host reservation with a DHCP client, you can select one of the identifier types supported by Kea. Available identifiers differ depending on whether the user selected DHCPv4 or DHCPv6 servers. The identifier can be specified using `hex` or `text` format. For example, the `hw-address` is typically specified as a string of hexadecimal digits: `ab:76:54:c6:45:31`. In that case, select `hex` option. Some identifiers, e.g. `circuit-id`, are often specified using “printable characters”, e.g. `circuit-no-1`. In that case, select `text` option. Please refer to [Host Reservations in DHCPv4](#) and [Host Reservations in DHCPv6](#) for more details regarding allowed DHCP identifiers and their formats.

Further in the form, you can specify the actual reservations. It is possible to specify at most one IPv4 address. In the case of the DHCPv6 servers, it is possible to specify multiple IPv6 addresses and delegated prefixes.

The DHCPv4 `siaddr`, `sname` and `file` fields can be statically assigned to the clients using host reservations. The relevant values in Kea and Stork are: **Next Server**, **Server Hostname**, and **Boot File Name**. You can only set these values for the DHCPv4 servers. The form lacks controls for setting them when editing a DHCPv6 host.

It is possible to associate one or more client classes with a host. Kea servers assign these classes to the DHCP packets received from the client having the host reservation. Client classes are typically defined in the Kea configurations but not necessarily. For example, built-in classes like **DROP** have no explicit definitions in the configuration files. You

can click the **List** button to select client classes from the list of classes explicitly defined in the configurations of the monitored Kea servers. Select the desired class names and click **Insert**. If the desired class name is not on the list, you can type the class name directly in the input box and press enter. Click on the cross icon next to the class name to delete it from the host reservation.

DHCP options can be added to the host reservation by clicking the **Add Option** button. The list of the standard DHCP options is available via the dropdown. However, if the list is missing a desired option, you can simply type the option code in the dropdown. The **Always Send** checkbox specifies whether the option should always be returned to a DHCP client assigned this host reservation, regardless of whether the client requests this option from the DHCP server.

Stork recognizes standard DHCP option formats. After selecting an option code, the form is adjusted to include option fields suitable for the selected option. If the option payload comprises an array of option fields, only the first field (or the first group of the record field) is displayed by default. Use the **Add <field-type>** button below the option code to add more fields to the array.

Note: Currently, Stork does not verify whether or not the specified options comply with the formats specified in the RFCs, nor does it check them against the runtime option definitions configured in Kea. If you specify wrong option format, Stork will try to send the option to Kea for verification, and Kea will reject the new reservation. The reservation can be submitted again after correcting the option payload.

Please use the **Add <field-type>** button to add suboptions to a DHCP option. Stork supports top-level options with maximum two levels of suboptions.

If a host reservation is configured in several DHCP servers, typically, all servers comprise the same set of parameters (i.e., IP addresses, hostname, boot fields, client classes and DHCP options). By default, creating a new host reservation for several servers sends an identical copy of the host reservation to each. You may choose to specify a different set of boot fields, client classes or options for different servers by selecting **Configure individual server values** at the top of the form. In this case, you must specify the complete sets of boot fields, client classes and options for each DHCP server. Leaving them blank for some servers means that these servers receive no boot fields, classes or DHCP options with the reservation.

3.5.6.5 Updating Host Reservations

In a selected host reservation's view, click **Edit** button to open a form for editing host reservation information. The form automatically toggles editing DHCP options individually for each server (see above) when it detects different option sets on different servers using the reservation. Besides editing the host reservation information, it is also possible to deselect some of the servers (using the DHCP Servers dropdown), which will delete the reservation from these servers.

Use the **Revert Changes** button to remove all applied changes and restore the original host reservation information. Use **Cancel** to close the form without applying the changes.

3.5.6.6 Deleting Host Reservations

To delete a host reservation from all DHCP servers for which it is configured, click on the reservation in the host reservations list. Find the **Delete** button and confirm the reservation deletion. Use it with caution because this operation cannot be undone. The reservation is removed from the DHCP servers' databases. It must be re-created to be restored.

Note: The **Delete** button is unavailable for host reservations configured in the Kea configuration files or when the reservations are configured in the host database, but the `host_cmds` hook library is not loaded.

3.5.7 Leases Search

Stork can search DHCP leases on monitored Kea servers, which is helpful for troubleshooting issues with a particular IP address or delegated prefix. It is also helpful in resolving lease allocation issues for certain DHCP clients. The search mechanism utilizes Kea control commands to find leases on the monitored servers. An operator must ensure that any Kea servers on which he intends to search the leases have the [lease commands hook library](#) loaded. Stork does not search leases on Kea instances without this library.

The leases search is available via the DHCP -> Leases Search menu. Enter one of the searched lease properties in the search box:

- IPv4 address, e.g. 192.0.2.3
- IPv6 address or delegated prefix without prefix length, 2001:db8::1
- MAC address, e.g. 01:02:03:04:05:06
- DHCPv4 Client Identifier, e.g. 01:02:03:04
- DHCPv6 DUID, e.g. 00:02:00:00:00:04:05:06:07
- Hostname, e.g. myhost.example.org

All identifier types can also be specified using the notation with spaces, e.g. 01 02 03 04 05 06, or the notation with hexadecimal digits only, e.g. 010203040506.

To search all declined leases, type `state:declined`. Be aware that this query may return a large result if there are many declined leases, and thus the query processing time may also increase.

Searching using partial text is currently unsupported. For example: searching by partial IPv4 address 192.0.2 is not accepted by the search box. Partial MAC address 01:02:03 is accepted but will return no results. Specify the complete MAC address instead, e.g. 01:02:03:04:05:06. Searching leases in states other than `declined` is also unsupported. For example, the text `state:expired-reclaimed` is not accepted by the search box.

The search utility automatically recognizes the specified lease type property and communicates with the Kea servers to find leases using appropriate commands. Each search attempt may result in several commands to multiple Kea servers; therefore, it may take several seconds or more before Stork displays the search results. If some Kea servers are unavailable or return an error, Stork shows leases found on the servers which returned success status, and displays a warning message containing the list of Kea servers that returned an error.

If the same lease is found on two or more Kea servers, the results list contains all that lease's occurrences. For example, if there is a pair of servers cooperating via the High Availability hook library, the servers exchange the lease information, and each of them maintains a copy of the lease database. In that case, the lease search on these servers typically returns two occurrences of the same lease.

To display the detailed lease information, click the expand button (>) in the first column for the selected lease.

3.5.8 Kea High Availability Status

When viewing the details of the Kea application for which High Availability (HA) is enabled (via the `libdhcp_ha.so` hook library), the High Availability live status is presented and periodically refreshed for the DHCPv4 and/or DHCPv6 daemon configured as primary or secondary/standby server. The status is not displayed for the server configured as an HA backup. See the [High Availability section in the Kea ARM](#) for details about the roles of the servers within the HA setup.

The following picture shows a typical High Availability status view displayed in the Stork UI.

The **local** server is the DHCP server (daemon) belonging to the application for which the status is displayed; the **remote** server is its active HA partner. The remote server belongs to a different application running on a different machine; this machine may or may not be monitored by Stork. The statuses of both the local and the remote servers are fetched by

High Availability

Local server	Remote server (4 seconds ago)
State: <i>load-balancing</i>	State: <i>load-balancing</i>
Role: <i>primary</i>	Role: <i>secondary</i>
Scopes served: <i>server1</i>	Scopes served: <i>(none)</i>

Note
The local server responds to the entire DHCP traffic.

sending the `status-get` command to the Kea server whose details are displayed (the local server). In the load-balancing and hot-standby modes, the local server periodically checks the status of its partner by sending it the `ha-heartbeat` command. Therefore, this information is not always up-to-date; its age depends on the heartbeat command interval (typically 10 seconds). The status of the remote server returned by Stork includes the age of the data displayed.

The Stork status information contains the role, state, and scopes served by each HA partner. In the usual HA case, both servers are in load-balancing state, which means that both are serving DHCP clients. If the remote server crashes, the local server transitions to the `partner-down` state, which will be reflected in this view. If the local server crashes, this will manifest itself as a communication problem between Stork and the server.

As of the Stork 0.8.0 release, the High Availability view also contains information about the heartbeat status between the two servers and information about failover progress.

The failover progress information is only presented when one of the active servers has been unable to communicate with the partner via the heartbeat exchange for a time exceeding the `max-heartbeat-delay` threshold. If the server is configured to monitor the DHCP traffic directed to the partner, to verify that the partner is not responding to this traffic before transitioning to the `partner-down` state, the number of “unacked” clients (clients which failed to get a lease), connecting clients (all clients currently trying to get a lease from the partner), and analyzed packets are displayed. The system administrator may use this information to diagnose why the failover transition has not taken place or when such a transition is likely to happen.

More about the High Availability status information provided by Kea can be found in the [Kea ARM](#).

3.5.9 Viewing the Kea Log

Stork offers a simple log-viewing mechanism to diagnose issues with monitored applications.

Note: This mechanism currently only supports viewing Kea log files; viewing BIND 9 logs is not yet supported. Monitoring other logging locations such as stdout, stderr, or syslog is also not supported.

Kea can be configured to log into multiple destinations. Different types of log messages may be output into different log files: syslog, stdout, or stderr. The list of log destinations used by the Kea application is available on the Kea App page. Click on the Kea app to view its logs. Next, select the Kea daemon by clicking on one of the tabs, e.g. the DHCPv4 tab. Scroll down to the Loggers section.

This section contains a table with a list of configured loggers for the selected daemon. For each configured logger, the logger's name, logging severity, and output location are presented. The possible output locations are: log file, stdout, stderr, or syslog. It is only possible to view the logs' output to the log files. Therefore, for each log file there is a link which leads to the log viewer showing the selected file's contents. The loggers which output to the stdout, stderr, and syslog are also listed, but links to the log viewer are not available for them.

Clicking on the selected log file navigates to its log viewer. By default, the viewer displays the tail of the log file, up to 4000 characters. Depending on the network latency and the size of the log file, it may take several seconds or more before the log contents are fetched and displayed.

The log viewer title bar comprises three buttons. The button with the refresh icon triggers a log-data fetch without modifying the size of the presented data. Clicking on the + button extends the size of the viewed log tail by 4000 characters and refreshes the data in the log viewer. Conversely, clicking on the - button reduces the amount of presented data by 4000 characters. Each time any of these buttons is clicked, the viewer discards the currently presented data and displays the latest part of the log file tail.

Please keep in mind that extending the size of the viewed log tail may cause slowness of the log viewer and network congestion as the amount of data fetched from the monitored machine increases.

3.5.10 Viewing the Kea Configuration as a JSON Tree

Kea uses JavaScript Object Notation (JSON) to represent its configuration in the configuration files and the command channel. Parts of the Kea configuration held in the [Configuration Backend](#) are also converted to JSON and returned over the control channel in that format. Diagnosis of issues with a particular server often begins by inspecting its configuration.

In the Kea App view, select the appropriate tab for the daemon configuration to be inspected, and then click on the Raw Configuration button. The displayed tree view comprises the selected daemon's configuration fetched using the Kea `config-get` command.

Note: The `config-get` command returns the configuration currently in use by the selected Kea server. It is a combination of the configuration read from the configuration file and from the config backend, if Kea uses the backend. Therefore, the configuration tree presented in Stork may differ (sometimes significantly) from the configuration file contents.

The nodes with complex data types can be individually expanded and collapsed. All nodes can also be expanded or collapsed by toggling the Expand button. When expanding nodes with many sub-nodes, they may be paginated to avoid degrading browser performance.

Click the Refresh button to fetch and display the latest configuration. Click Download to download the entire configuration into a text file.

Note: Some of the configuration fields may contain sensitive data (e.g. passwords or tokens). The content of these fields is hidden, and a placeholder is shown. Configurations downloaded as JSON files by users other than super-admins contain null values in place of the sensitive data.

3.5.11 Configuration Review

Kea DHCP servers are controlled by numerous configuration parameters. It poses a risk of misconfiguration or inefficient server operation when the parameters are misused. Stork can help determine typical problems in a Kea server configuration using built-in configuration checkers.

It generates configuration reports for a monitored Kea daemon when it detects its configuration has changed. To view the reports for the daemon, navigate to the application page and select one of the daemons. The **Configuration Review Reports** panel lists issues and proposed configuration updates generated by the configuration checkers. Each checker focuses on one particular problem.

If you consider some of the reports false alarms in your deployment, you can disable some configuration checkers for a selected daemon or globally for all daemons. Click the **Checkers** button to open the list of available checkers and their current state. Click on the values in the **State** column for the respective checkers until they are in the desired states. Besides enabling and disabling the checker, it is possible to configure it to use the globally specified setting (i.e., globally enabled or globally disabled). The global settings control the checker states for all daemons for which explicit states are not selected.

Select **Configuration -> Review Checkers** from the main menu to modify the global states. Use the checkboxes in the **State** column to modify the global states for respective checkers.

The **Selectors** listed for each checker inform about the types of daemons whose configurations they validate:

- **each-daemon** - run for all types of daemons,
- **kea-daemon** - run for all Kea daemons,
- **kea-ca-daemon** - run for Kea Control Agents,
- **kea-dhcp-daemon** - run for DHCPv4 and DHCPv6 daemons,
- **kea-dhcp-v4-daemon** - checkers run for Kea DHCPv4 daemons,
- **kea-dhcp-v6-daemon** - run for Kea DHCPv6 daemons
- **kea-d2-daemon** - run for Kea D2 daemons,
- **bind9-daemon** - run for Bind 9 daemons

The **triggers** inform in which cases the checkers are executed. Currently, there are three types of triggers:

- **manual** - run on user's request,
- **config change** - run when daemon configuration change has been detected,
- **host reservations change** - run when a change in the Kea host reservations database has been detected.

The selectors and triggers are not configurable by a user.

3.5.12 Synchronizing Kea Configurations

Stork pullers periodically check Kea configurations against the local copies stored in the Stork database. These local copies are only updated when Stork detects any mismatch. This approach works fine in most cases and eliminates the overhead of unnecessarily updating the local database. However, there are possible scenarios when the mismatch between the configurations is not detected, but it is still desired to fetch and repopulate the configurations from the Kea servers to Stork.

There are many internal operations in Stork occurring when the configuration change has been detected (e.g., populating host reservations, log viewer initialization, configuration reviews, and many others). Resynchronizing the configurations from Kea triggers all these tasks. It may possibly correct some data integrity issues that may sometimes occur due to software bugs, network errors, or any other reason.

To schedule the configuration synchronization from the Kea servers, navigate to **Services** and then **Kea Apps**. Click on **Resynchronize Kea Configs** button. The pullers will fetch and populate the updated configuration data, but depending on the configured puller intervals, it will take some time. Ensure the pullers are not disabled on the **Settings** page; otherwise, the configurations will never re-synchronize.

3.6 Dashboard

The main Stork page presents a dashboard. It contains a panel with information about DHCP and a panel with events observed or noticed by the Stork server.

3.6.1 DHCP Panel

The DHCP panel includes two sections: one for DHCPv4 and one for DHCPv6. Each section contains three kinds of information:

- a list of up to five subnets with the highest pool utilization.
- a list of up to five shared networks with the highest pool utilization
- statistics about DHCP.

3.6.2 Events Panel

The Events panel presents the list of the most recent events captured by the Stork server. There are three event urgency levels: info, warning, and error. Events pertaining to the particular entities, e.g. machines or applications, provide a link to a web page containing information about the given object.

3.7 Events Page

The Events page presents a list of all events. It allows events to be filtered by:

- urgency level
- machine
- application type (Kea, BIND 9)
- daemon type (DHCPv4, DHCPv6, named, etc.)
- the user who caused given event (available only to users in the `super-admin` group).

TROUBLESHOOTING

4.1 stork-agent

This section describes the solutions for some common issues with the Stork agent.

Issue

A machine is authorized in the Stork server successfully, but there are no applications.

Description

The user installed and started `stork-server` and `stork-agent` and authorized the machine. The “Last Refreshed” column has a value on the Machines page, the “Error” column value shows no errors, but the “Daemons” column is still blank. The “Application” section on the specific Machine page is also blank.

Solution

Make sure that the daemons are running:

- Kea Control Agent, Kea DHCPv4 server, and/or Kea DHCPv6 server
- BIND 9

Stork looks for the processes named `kea-ctrl-agent` (for Kea) or `named` (for BIND 9). Make sure those processes are running and are named appropriately. You may use the `ps aux` (or similar) command to debug if the processes are running. Currently Stork does not support detecting off-line services. If BIND 9 is located in an uncommon location and Stork agent is unable to detect it, there are two steps that may be helpful. You may enable DEBUG logging level, so the agent will print more detailed information about locations being checked.

For BIND9, the detection process consists of four steps. The next step is only performed if the previous one failed. The steps are:

1. Try to parse `-c` parameter of the running process;
2. Use `STORK_BIND9_CONFIG` environment variable;
3. Try to parse output of the `named -V` command;
4. Try to find `named.conf` in the default locations.

You may define `STORK_BIND9_CONFIG` environment variable to specify exact location of the BIND 9 configuration file.

For BIND 9, make sure that the `rndc` channel is enabled. By default, it is enabled, even if the `controls` clause is missing. Stork is able to detect default values, so typically there is no administrative action required, unless the `rndc` channel was explicitly disabled. Make sure the `rndc` key is readable by Stork agent.

Also, make sure that BIND 9 has statistics channel enabled. That is done by adding `statistics-channels` entry. Typically, this looks like the following:

```
statistics-channels {  
    inet 127.0.0.1 port 8053 allow { 127.0.0.1; };  
};
```

but it may vary greatly, depending on your setup. Please consult BIND 9 ARM for details.

Explanation

If the “Last Refreshed” column has a value, and the “Error” column value has no errors, the communication between `stork-server` and `stork-agent` works correctly, which implies that the cause of the problem is between the Stork agent and the daemons. The most likely issue is that none of the Kea/BIND 9 daemons are running. `stork-agent` communicates with the BIND 9 daemon directly; however, it communicates with the Kea DHCPv4 and Kea DHCPv6 servers via the Kea Control Agent. If only the “CA” daemon is displayed in the Stork interface, the Kea Control Agent is running, but the DHCP daemons are not.

Issue

After starting the Stork agent, it gets stuck in an infinite “sleeping” loop.

Description

`stork-agent` is running with server support (the `--listen-prometheus-only` flag is unused). The try to register agent in Stork server message is displayed initially, but the agent only prints the recurring sleeping for 10 seconds before next registration attempt message.

Solution 1.

`stork-server` is not running. Start the Stork server first and restart the `stork-agent` daemon.

Solution 2.

The configured server URL in `stork-agent` is invalid. Correct the URL and restart the agent.

Issue

After starting `stork-agent`, it keeps printing the following messages: loaded server cert: `/var/lib/stork-agent/certs/cert.pem` and key: `/var/lib/stork-agent/certs/key.pem`

Description

`stork-agent` runs correctly, and its registration is successful. After the started serving Stork Agent message, the agent prints the recurring message about loading server certs. The network traffic analysis to the server reveals that it rejects all packets from the agent (TLS HELLO handshake failed).

Solution

Re-register the agent to regenerate the certificates, using the `stork-agent register` command.

Explanation

The `/var/lib/stork-agent/certs/ca.pem` file is missing or corrupted. The re-registration removes old files and creates new ones.

Issue

The cert PEM file is not loaded.

Description

The agent fails to start and prints an open `/var/lib/stork-agent/certs/cert.pem: no such file or directory` could not load cert PEM file: `/var/lib/stork-agent/certs/cert.pem` error message.

Solution

Re-register the agent to regenerate the certificates, using the `stork-agent register` command.

Issue

A connection problem to the DHCP daemon(s).

Description

The agent prints the message `problem with connecting to dhcp daemon: unable to forward command to the dhcp6 service: No such file or directory`. The server is likely to be offline.

Solution 1

Try to start the Kea service: `systemctl start kea-dhcp4 kea-dhcp6`

Solution 2

Ensure that the `control-socket` entry is specified in the Kea DHCP configuration file (`kea-dhcp4.conf` or `kea-dhcp6.conf`)

Explanation

The `kea-dhcp4.service` or `kea-dhcp6.service` (depending on the service type in the message) may be not running. If the DHCP daemon is running and operational (it allocates the leases), but the problem is still occurring, inspect the DHCP daemon configuration file (`kea-dhcp4.conf` or `kea-dhcp6.conf`). The file must contain the top-level `control-socket` property with valid content. See the Kea [DHCPv4](#) or [DHCPv6](#) ARM for details. This property is missing by default if you install Kea from the Debian/Ubuntu repository. To avoid this and similar problems, we recommend to use our official packages available on [CloudSmith](#).

Issue

`stork-agent` receives a remote error: `tls: certificate required` message from the Kea Control Agent.

Description

The Stork agent and the Kea Control Agent are running, but they cannot establish a connection. The `stork-agent` log contains the error message mentioned above.

Solution

Install the valid TLS certificates in `stork-agent` or set the `cert-required` value in `/etc/kea/kea-ctrl-agent.conf` to `false`.

Explanation

By default, `stork-agent` does not use TLS when it connects to Kea. If the Kea Control Agent configuration includes the `cert-required` value set to `true`, it requires the Stork agent to use secure connections with valid, trusted TLS certificates. It can be turned off by setting the `cert-required` value to `false` when using self-signed certificates, or the Stork agent TLS credentials can be replaced with trusted ones.

Issue

Kea Control Agent returns a Kea error response - `status: 401, message: Unauthorized message`.

Description

The Stork agent and the Kea Control Agent are running, but they cannot connect. The `stork-agent` logs contain similar messages: `failed to parse responses from Kea: { "result": 401, "text": "Unauthorized" }` or `Kea error response - status: 401, message: Unauthorized`.

Solution

Update the `/etc/stork/agent-credentials.json` file with the valid user/password credentials.

Explanation

The Kea Control Agent can be configured to use Basic Authentication. If it is enabled, valid credentials must be provided in the `stork-agent` configuration. Verify that this file exists and contains a valid username, password, and IP address.

Issue

During the registration process, `stork-agent` prints a problem with registering machine: cannot parse address message.

Description

Stork is configured to use an IPv6 link-local address. The agent prints the `try to register agent in Stork server` message and then the above error. The agent exists with a fatal status.

Solution

Use a global IPv6 or an IPv4 address.

Explanation

IPv6 link-local addresses are not supported by `stork-server`.

Issue

A protocol problem occurs during the agent registration.

Description

During the registration process, `stork-agent` prints a problem with registering machine: `Post "/api/machines": unsupported protocol scheme ""` message.

Solution

The `--server-url` argument is provided in the wrong format; it must be a canonical URL. It should begin with the protocol (`http://` or `https://`), contain the host (DNS name or IP address; for IPv6 escape them with square brackets), and end with the port (delimited from the host by a colon). For example: `http://storkserver:8080`.

Issue

The values in `/etc/stork/agent.env` or `/etc/stork/agent-credentials.json` were changed, but `stork-agent` does not noticed the changes.

Solution 1.

Restart the daemon.

Solution 2.

Send the SIGHUP signal to the `stork-agent` process.

Explanation

`stork-agent` reads configurations at startup or after receiving the SIGHUP signal.

Issue

The values in `/etc/stork/agent.env` were changed and the Stork agent was restarted, but it still uses the default values.

Description

The agent is running using the `stork-agent` command. It uses the parameters passed from the command line but ignores the `/etc/stork/agent.env` file entries. If the agent is running as the `systemd` daemon, it uses the expected values.

Solution 1.

Load the environment variables from the `/etc/stork/agent.env` file before running Stork agent. For example, run `. /etc/stork/agent.env`.

Solution 2.

Run the Stork agent with the `--use-env-file` switch.

Explanation

The `/etc/stork/agent.env` file contains the environment variables, but `stork-agent` does not automatically load them, unless you use `--use-env-file` flag; the file must be loaded manually. The default `systemd` service unit is configured to load this file before starting the agent.

Issue

Stork shows only Kea Control Agent tab on the application page. It detects no Kea DHCP servers, although the DHCP daemons are running and allocating leases.

Description

There are only a single tab titled “CA” on the Kea application page but no data about any DHCP daemon or DDNS. The Kea Control Agent and Kea DHCPv4 or Kea DHCPv6 daemon are running and serve leases. The Stork agent logs comprises the The Kea application has no DHCP daemons configured message.

Solution

The `kea-ctrl-agent.conf` file misses the `control-sockets` property.

Explanation

Stork detects Kea components using the control socket list from the Kea Control Agent configuration file. The list must be configured properly to allow Stork to send commands to Kea daemons. See *Kea ARM* <<https://kea.readthedocs.io/en/latest/arm/agent.html#configuration>> for details. This property is missing by default if you install Kea from the Debian/Ubuntu repository. To avoid this and similar problems, we recommend to use our official packages available on [CloudSmith](#).

Issue

Stork agent doesn't start with the following error: failed to load hooks from directory: '[HOOK DIRECTORY]': plugin.Open("[HOOK DIRECTORY]/[FILENAME]"): [HOOK DIRECTORY]/[FILENAME]: file too short or failed to load hooks from directory: '[HOOK DIRECTORY]': plugin.Open("[HOOK DIRECTORY]/[FILENAME]"): [HOOK DIRECTORY]/[FILENAME]: invalid ELF header

Solution

Remove the given file from the hook directory.

Explanation

The file under a given path is not valid Stork hook.

Issue

Stork agent doesn't start with the following error: `Cannot start the Stork Agent: incompatible hook version: 1.0.0`

Solution

Update the given hook.

Explanation

The hook is out-of-date. It's incompatible with the Stork core application.

Issue

Stork agent doesn't start with the following error: `Cannot start the Stork Agent: plugin: symbol Version not found in plugin`

Solution

Remove or fix the given file.

Explanation

Hook directory contains Go plugin but that is not a hook; Hook doesn't contain required symbol.

Issue

Stork agent doesn't start with the following error: `Cannot start the Stork Agent: hook library dedicated for another program: Stork Server`

Solution

Move the incompatible hooks to a separate directory.

Explanation

Stork agent requires the hook directory to contain only agent hooks. The above error message indicates that the hook directory contains hooks dedicated to the Stork server.

Issue

Stork agent starts but the hooks aren't loaded. The logs comprise the following message: `Cannot find plugin paths in: /var/lib/stork-agent/hooks: cannot list hook directory: /var/lib/stork-agent/hooks: open /var/lib/stork-agent/hooks: no such file or directory`

Solution

Create the hook directory or change the path in the configuration.

Explanation

Hook directory doesn't exist.

Issue

Stork agent doesn't start with the following error: `Cannot start the Stork Agent: open [HOOK DIRECTORY]: permission denied cannot list hook directory`

Solution

Grant the right for read the hook directory for the Stork user.

Explanation

The hook directory is not readable.

Issue

Stork agent doesn't start with the following error: Cannot start the Stork Agent: readdirent [HOOK DIRECTORY]/[FILENAME]: not a directory cannot list hook directory

Solution

Change the hook directory path.

Explanation

File was found instead of directory under given hook directory path.

4.2 stork-server

This section describes the solutions for some common issues with the Stork server.

Issue

The values in `/etc/stork/server.env` were changed, but `stork-server` does not noticed the changes.

Solution 1.

Restart the daemon.

Solution 2.

Send the SIGHUP signal to the `stork-server` process.

Explanation

`stork-server` reads configurations at startup or after receiving the SIGHUP signal.

Issue

The values in `/etc/stork/server.env` were changed and the Stork server was restarted, but it still uses the default values.

Description

The server is running using the `stork-server` command. It uses the parameters passed from the command line but ignores the `/etc/stork/server.env` file entries. If the server is running as the `systemd` daemon, it uses the expected values.

Solution 1.

Load the environment variables from the `/etc/stork/server.env` file before running Stork server. For example, run `. /etc/stork/server.env`.

Solution 2.

Run the Stork server with the `--use-env-file` switch.

Explanation

The `/etc/stork/server.env` file contains the environment variables, but `stork-server` does not automatically load them, unless you use `--use-env-file` flag; the file must be loaded manually. The default `systemd` service unit is configured to load this file before starting the agent.

Issue

The server is running but rejects the HTTP requests due to the TLS handshake error.

Description

The HTTP requests sent via an Internet browser or tools like curl are rejected. The clients show a message similar to: `OpenSSL SSL_write: Broken pipe, errno 32`. The Stork server logs contain the TLS handshake error entry with the `tls: client didn't provide a certificate` description.

Solution 1.

Leave the `STORK_REST_TLS_CA_CERTIFICATE` environment variable and the `--rest-tls-ca` flag empty.

Solution 2.

Configure the Internet browser or HTTP tool to use the valid and trusted TLS client certificate. The client certificate must be signed by the authority whose CA certificate was provided in the server configuration.

Explanation

Providing the `STORK_REST_TLS_CA_CERTIFICATE` environment variable or the `--rest-tls-ca` flag turns on the TLS client certificate verification. The HTTP requests must be assigned with the valid and trusted HTTP certificate signed by the authority whose CA certificate was provided in the server configuration. Otherwise, the request will be rejected. This option is dedicated to improving server security by limiting access to only trusted users. You shouldn't use it if you don't have a CA configured or want to allow to login to the Stork server from any computer without prior setup.

Issue

Server doesn't start and prints the `permission denied for schema public` message.

Description

The fresh installation of the Stork server is made, and the database is empty. The Stork server doesn't start, and the Stork tool returns an error on the database migration. The logs reveal the denied access to the schema public.

Solution 1.

Execute the `GRANT ALL ON DATABASE stork_db TO stork_user;` on the Stork database (replace `stork_db` and `stork_user` with the proper names).

Solution 2.

Perform migration using Stork tool with the maintenance (e.g., superuser) database credentials.

Explanation

In some Postgres installations (by default in Postgres 15 and above), the `CREATE` permission is not initially granted to all users except the database owner. The stork server needs this permission to perform the database migration on startup. You can grant this permission or use the Stork tool to migrate the schema as the maintenance database user (e.g., superuser).

Issue

Stork server doesn't start with the following error: `Cannot start the Stork Server: failed to load hooks from directory: '[HOOK DIRECTORY]': plugin.Open("[HOOK DIRECTORY]/[FILENAME]"): [HOOK DIRECTORY]/[FILENAME]: file too short` or `Cannot start the Stork Server: failed to load hooks from directory: '[HOOK DIRECTORY]': plugin.Open("[HOOK DIRECTORY]/[FILENAME]"): [HOOK DIRECTORY]/[FILENAME]: invalid ELF header`

Solution

Remove the given file from the hook directory.

Explanation

The file under a given path is not valid Stork hook.

Issue

Stork server doesn't start with the following error: `Cannot start the Stork Server: incompatible hook version: 1.0.0`

Solution

Update the given hook.

Explanation

The hook is out-of-date. It's incompatible with the Stork core application.

Issue

Stork server doesn't start with the following error: `Cannot start the Stork Server: plugin: symbol Version not found in plugin`

Solution

Remove or fix the given file.

Explanation

Hook directory contains Go plugin but that is not a hook; Hook doesn't contain required symbol.

Issue

Stork server doesn't start with the following error: `Cannot start the Stork Server: hook library dedicated for another program: Stork Agent`

Solution

Move the incompatible hooks to a separate directory.

Explanation

Stork server requires the hook directory to contain only server hooks. The above error message indicates that the hook directory contains hooks dedicated to the Stork agent.

Issue

Stork server starts but the hooks aren't loaded. The logs comprise the following message: `Cannot find plugin paths in: /var/lib/stork-server/hooks: cannot list hook directory: /var/lib/stork-server/hooks: open /var/lib/stork-server/hooks: no such file or directory`

Solution

Create the hook directory or change the path in the configuration.

Explanation

Hook directory doesn't exist.

Issue

Stork server doesn't start with the following error: `Cannot start the Stork Server: open [HOOK DIRECTORY]: permission denied cannot list hook directory`

Solution

Grant the right for read the hook directory for the Stork user.

Explanation

The hook directory is not readable.

Issue

Stork server doesn't start with the following error: Cannot start the Stork Server:
readdir [HOOK DIRECTORY]/[FILENAME]: not a directory cannot list hook
directory

Solution

Change the hook directory path.

Explanation

File was found instead of directory under given hook directory path.

BACKEND API

`stork-agent` provides a RESTful API, generated using [Swagger](#). Source YAML files are stored in the `api/` directory in the source files. To view the RESTful API documentation, open the Stork interface, click Help, and choose Stork API Docs (SwaggerUI) or Stork API Docs (Redoc).

DEMO

A sample installation of Stork can be used to demonstrate its capabilities, and can also be used for its development.

The demo installation uses Docker and Docker Compose to set up all Stork services. It contains:

- Stork Server
- Stork Agent with Kea DHCPv4
- Stork Agent with Kea DHCPv6
- Stork Agent with Kea HA-1 (high availability server 1)
- Stork Agent with Kea HA-2 (high availability server 2)
- Stork Agent with Kea Using Many Subnets
- Stork Agent with BIND 9
- Stork Agent with BIND 9-2
- Stork Environment Simulator
- PostgreSQL database
- Prometheus & Grafana

These services allow observation of many Stork features.

6.1 Requirements

Running the Stork demo requires the same dependencies as building Stork, which are described in the *Installing From Sources* chapter.

Besides the standard dependencies, the Stork demo requires:

- Docker
- Docker Compose

For details, please see the Stork wiki at <https://gitlab.isc.org/isc-projects/stork/-/wikis/Processes/development-Environment>

6.2 Setup Steps

The following command retrieves all required software (Go, go-swagger, Node.js, Angular dependencies, etc.) to the local directory. No root password is necessary. It then prepares Docker images and starts them.

```
$ rake demo:up
```

Once the build process finishes, the Stork UI is available at <http://localhost:8080/>. Use any browser to connect.

The `stork-demo.sh` script can be used to start the demo without the Ruby toolkit:

```
$ ./stork-demo.sh
```

6.2.1 Premium Features

It is possible to run the demo with premium features enabled in the Kea apps; it requires the demo to be started with an access token for the Kea premium repositories. Access tokens are provided to ISC's paid support customers and format-specific setup instructions can be found on <https://cloudsmith.io/~isc/repos/kea-2-4-prv/setup/#tab-formats-deb>. ISC paid support customers should feel free to open a ticket for assistance if needed.

```
$ rake demo:up CS_REPO_ACCESS_TOKEN=<access token>
```

6.2.2 Detached Mode

It is possible to start the demo in detached mode. In that case, it does not depend on the terminal and runs in the background until the `rake demo:down` call. To enable the detached mode, specify the `DETACH` variable set to `true`.

```
$ rake demo:up DETACH=true
```

6.3 Demo Containers

The setup procedure creates several Docker containers. Their definition is stored in the `docker-compose.yaml` file in the Stork source code repository.

These containers have Stork production services and components:

server

This container is essential. It runs `stork-server`, which interacts with all the agents and the database and exposes the API. Without it, Stork is not able to function.

webui

This container is essential in most circumstances. It provides the front-end web interface. It is potentially unnecessary with the custom development of a Stork API client. The content is served by Nginx.

webui-apache

This container is similar to the previous one, except Apache serves it, and the web UI is available under the `/stork` sub-directory, port 8081.

agent-bind9

This container runs a BIND 9 server. With this container, the agent can be added as a machine and Stork will begin monitoring its BIND 9 service.

agent-bind9-2

This container also runs a BIND 9 server, for the purpose of experimenting with two different DNS servers.

agent-kea

This container runs a Kea DHCPv4 server. With this container, the agent can be added as a machine and Stork will begin monitoring its Kea DHCPv4 service.

agent-kea6

This container runs a Kea DHCPv6 server.

agent-kea-ha1 and agent-kea-ha2

These two containers should, in general, be run together. They each have a Kea DHCPv4 server instance configured in an HA pair. With both instances running and registered as machines in Stork, users can observe certain HA mechanisms, such as one partner taking over the traffic if the other partner becomes unavailable.

agent-kea-many-subnets

This container runs an agent with a Kea DHCPv4 server that has many (nearly 7000) subnets defined in its configuration.

agent-kea-premium-one and agent-kea-premium-two

These containers run agents with Kea DHCPv4 and DHCPv6 servers connected to a MySQL database containing host reservations. They are only available when premium features have been enabled during the demo build.

These are containers with third-party services that are required by Stork:

postgres

This container is essential. It runs the PostgreSQL database that is used by `stork-server` and the Kea containers. Without it, `stork-server` produces error messages about an unavailable database.

prometheus

Prometheus, a monitoring solution (<https://prometheus.io/>), uses this container to monitor applications. It is preconfigured to monitor the Kea and BIND 9 containers.

grafana

This is a container with Grafana (<https://grafana.com/>), a dashboard for Prometheus. It is preconfigured to pull data from a Prometheus container and show Stork dashboards.

mariadb

This container is essential. It runs the MariaDB database that is used by the Kea containers.

There is also a supporting container:

simulator

Stork Environment Simulator is a web application that can run DHCP traffic using `perfdhcp` (useful to observe non-zero statistics coming from Kea), run DNS traffic using `dig` and `flamethrower` (useful to observe non-zero statistics coming from BIND 9), and start and stop any service in any other container (useful to simulate, for example, a Kea crash).

dns-proxy-server

Used only when the Stork Agent from container connects to a locally running server. The Kea/Bind containers use internal Docker hostnames that the host cannot resolve. We run the DNS proxy in the background that translates the Docker hostnames to valid IP addresses.

Note: The containers running the Kea and BIND 9 applications are for demonstration purposes only. They allow users to quickly start experimenting with Stork without having to manually deploy Kea and/or BIND 9 instances.

The PostgreSQL database schema is automatically migrated to the latest version required by the `stork-server` process.

The setup procedure assumes those images are fully under Stork's control. Any existing images are overwritten.

6.4 Initialization

stork-server requires some initial information:

1. Go to <http://localhost:8080/machines/all>
2. Add new machines (leave the default port):
 1. agent-kea
 2. agent-kea6
 3. agent-kea-ha1
 4. agent-kea-ha2
 5. agent-bind9
 6. agent-bind9-2

6.5 Stork Environment Simulator

The Stork Environment Simulator demonstrates how Stork:

- sends DHCP traffic to Kea applications
- sends DNS requests to BIND 9 applications
- stops and starts Stork agents and the Kea and BIND 9 daemons

The Stork Environment Simulator allows DHCP traffic to be sent to selected subnets pre-configured in Kea instances, with a limitation: it is possible to send traffic to only one subnet from a given shared network.

The Stork Environment Simulator also allows demonstration DNS traffic to be sent selected DNS servers.

The Stork Environment Simulator can add all the machines available in the demo setup. It can stop and start selected Stork agents and the Kea and BIND 9 applications. This is useful to simulate communication problems between applications, Stork agents, and the Stork server.

The Stork Environment Simulator can be found at port 5010 when the demo is running.

6.6 Prometheus

The Prometheus instance is preconfigured in the Stork demo and pulls statistics from:

- the node exporters: agent-kea:9100, agent-bind9:9100, agent-bind9:9100
- the Kea exporters embedded in stork-agent: agent-kea:9547, agent-kea6:9547, agent-kea-ha1:9547, agent-kea-ha2:9547
- the BIND exporters embedded in stork-agent: agent-bind9:9119, agent-bind9-2:9119

The Prometheus web page can be found at: <http://localhost:9090/>.

6.7 Grafana

The Grafana instance is also preconfigured in the Stork demo. It pulls data from Prometheus and loads dashboards from the Stork repository, in the Grafana folder.

The Grafana web page can be found at: <http://localhost:3000/>.

MANUAL PAGES

7.1 stork-server - Main Stork Server

7.1.1 Synopsis

stork-server [-h] [-v] [-m] [-u] [-dbhost] [-p] [-d] [-db-sslmode] [-db-sslcert] [-db-sslkey] [-db-sslrootcert] [-db-trace-queries=] [-rest-cleanup-timeout] [-rest-graceful-timeout] [-rest-max-header-size] [-rest-host] [-rest-port] [-rest-listen-limit] [-rest-keep-alive] [-rest-read-timeout] [-rest-write-timeout] [-rest-tls-certificate] [-rest-tls-key] [-rest-tls-ca] [-rest-static-files-dir]

7.1.2 Description

stork-server provides the main Stork server capabilities. In every Stork deployment, there should be exactly one Stork server.

7.1.3 Arguments

stork-server takes the following arguments (equivalent environment variables are listed in square brackets, where applicable):

-h|--help

Returns the list of available parameters.

-v|--version

Returns the **stork-server** version.

--hook-directory

The path to the hook directory. [**\$STORK_SERVER_HOOK_DIRECTORY**]

--env-file

Environment file location; applicable only if the **use-env-file** is provided. The default is **/etc/stork/server.env**.

--use-env-file

Read the environment variables from the environment file. The default is **false**.

-m|--metrics

Enables the periodic metrics collector and **/metrics** HTTP endpoint for Prometheus. This endpoint requires no authentication; it is recommended to restrict external access to it (e.g. using the HTTP proxy). It is disabled by default. [**\$STORK_SERVER_ENABLE_METRICS**]

--initial-puller-interval

Default interval used by pullers fetching data from Kea. If not provided the recommended values for each puller are used. [STORK_SERVER_INITIAL_PULLER_INTERVAL]

-u|--db-user

Specifies the user name to be used for database connections. The default is `stork`. [STORK_DATABASE_USER_NAME]

--db-password=

Specifies the database password for database connections. If not specified, the user will be prompted for the password if necessary. [STORK_DATABASE_PASSWORD]

--db-url

Specifies the URL to locate and connect to database. It's mutually exclusively with the host, port, username, and password. [STORK_DATABASE_URL]

--db-host

Specifies the name of the host, IP address or a socket path for the database connection. The default value depends on the system. [STORK_DATABASE_HOST]

-p|--db-port

Specifies the port on which the database is available. The default is 5432. [STORK_DATABASE_PORT]

-d|--db-name=

Specifies the name of the database to connect to. The default is `stork`. [STORK_DATABASE_NAME]

--db-sslmode

Specifies the SSL mode for connecting to the database; possible values are `disable`, `require`, `verify-ca` or `verify-full`. The default is `disable`. [STORK_DATABASE_SSLMODE] Acceptable values are:

`disable` Disables encryption between the Stork server and the PostgreSQL database.

`require` Uses secure communication but does not verify the server's identity, unless the root certificate location is specified and that certificate exists. If the root certificate exists, the behavior is the same as in the case of `verify-ca`.

`verify-ca` Uses secure communication and verifies the server's identity by checking it against the root certificate stored on the Stork server machine.

`verify-full` Uses secure communication and verifies the server's identity against the root certificate. In addition, checks that the server hostname matches the name stored in the certificate.

--db-sslcert

Specifies the location of the SSL certificate used by the server to connect to the database. [STORK_DATABASE_SSLCERT]

--db-sslkey

Specifies the location of the SSL key used by the server to connect to the database. [STORK_DATABASE_SSLKEY]

--db-sslrootcert

Specifies the location of the root certificate file used to verify the database server's certificate. [STORK_DATABASE_SSLROOTCERT]

--db-trace-queries=

Enables tracing of SQL queries. Possible values are `run` - only runtime, without migrations, `all` - both migrations and runtime, or `none` - disable the query logging. [STORK_DATABASE_TRACE]

--rest-cleanup-timeout

Specifies the period to wait, in seconds, before killing idle connections. The default is 10.

--rest-graceful-timeout

Specifies the period to wait, in seconds, before shutting down the server. The default is 15.

--rest-max-header-size

Specifies the maximum number of bytes the server reads when parsing the request header's keys and values, including the request line. It does not limit the size of the request body. The default is 1024 (1MB).

--rest-host

Specifies the IP address to listen on for connections over the RESTful API. [STORK_REST_HOST]

--rest-port

Specifies the port to listen on for connections over the RESTful API. The default is 8080. [STORK_REST_PORT]

--rest-listen-limit

Specifies the maximum number of outstanding requests.

--rest-keep-alive

Specifies the TCP keep-alive timeout, in minutes, on accepted connections. After this period, the server prunes dead TCP connections (e.g. when a laptop is closed mid-download). The default is 3.

--rest-read-timeout

Specifies the maximum duration, in seconds, before timing out a read of the request. The default is 30.

--rest-write-timeout

Specifies the maximum duration, in seconds, before timing out a write of the response. The default is 60.

--rest-tls-certificate

Specifies the certificate to use for secure connections. [STORK_REST_TLS_CERTIFICATE]

--rest-tls-key

Specifies the private key to use for secure connections. [STORK_REST_TLS_PRIVATE_KEY]

--rest-tls-ca

Specifies the Certificate Authority file to be used with a mutual TLS authority. [STORK_REST_TLS_CA_CERTIFICATE]

--rest-static-files-dir

Specifies the directory with static files for the UI. [STORK_REST_STATIC_FILES_DIR]

--rest-base-url

The base URL of the UI. Specify this flag if the UI is served from a subdirectory (not the root URL). It must start and end with a slash. Example: <https://www.example.com/admin/stork/> would need to have '/admin/stork/' as the base url. The default is /. [STORK_REST_BASE_URL]

Note that there is no argument for the database password, as the command-line arguments can sometimes be seen by other users. It can be passed using the STORK_DATABASE_PASSWORD variable.

Stork logs on INFO level by default. Other levels can be configured using the STORK_LOG_LEVEL variable. Allowed values are: DEBUG, INFO, WARN, ERROR.

To control the logging colorization, Stork supports the CLICOLOR and CLICOLOR_FORCE standard UNIX environment variables. Use CLICOLOR_FORCE to enforce enabling or disabling the ANSI colors usage. Set CLICOLOR to 0 or false to disable colorization even if the TTY is attached.

The highest priority always have the command line flags. The parameters from the environment file take precedence over the environment variables if the --use-env-file flag is used.

7.1.4 Mailing Lists and Support

There are public mailing lists available for the Stork project. **stork-users** (stork-users at lists.isc.org) is intended for Stork users. **stork-dev** (stork-dev at lists.isc.org) is intended for Stork developers, prospective contributors, and other advanced users. The lists are available at <https://www.isc.org/maillinglists/>. The community provides best-effort support on both of those lists.

7.1.5 History

stork-server was first coded in November 2019 by Michal Nowikowski and Marcin Siodelski.

7.1.6 See Also

stork-agent(8)

7.2 stork-agent - Stork Agent to Monitor BIND 9 and Kea services

7.2.1 Synopsis

stork-agent [-listen-stork-only] [-listen-prometheus-only] [-v] [-host=] [-port=] [-skip-tls-cert-verification=] [-prometheus-kea-exporter-address=] [-prometheus-kea-exporter-port=] [-prometheus-kea-exporter-interval=] [-h]

stork-agent register [-server-url=] [-server-token] [-agent-host=]

7.2.2 Description

The **stork-agent** is a small tool that operates on systems that are running BIND 9 or Kea services. The Stork server connects to the Stork agent and uses it to monitor services remotely.

7.2.3 Arguments

Stork does not use an explicit configuration file. Instead, its behavior can be controlled with command-line switches and/or variables. The Stork agent takes the following command-line switches. Equivalent environment variables are listed in square brackets, where applicable.

--listen-stork-only

Instructs **stork-agent** to listen for commands from the Stork server, but not for Prometheus requests.
[\$STORK_AGENT_LISTEN_STORK_ONLY]

--listen-prometheus-only

Instructs **stork-agent** to listen for Prometheus requests, but not for commands from the Stork server.
[\$STORK_AGENT_LISTEN_PROMETHEUS_ONLY]

--hook-directory

The path to the hook directory. [\$STORK_AGENT_HOOK_DIRECTORY]

--env-file

Environment file location; applicable only if the use-env-file is provided. The default is /etc/stork/agent.env.

--use-env-file

Read the environment variables from the environment file. The default is false.

-v|--version

Returns the software version.

-h or --help

Returns the list of available parameters.

Stork server flags:

--host=

Specifies the IP address or hostname to listen on for incoming Stork server connections. [STORK_AGENT_HOST]

--port=

Specifies the TCP port to listen on for incoming Stork server connections. The default is 8080. [STORK_AGENT_PORT]

--skip-tls-cert-verification=

Indicates that TLS certificate verification should be skipped when the Stork agent makes HTTP calls over TLS. The default is false. [STORK_AGENT_SKIP_TLS_CERT_VERIFICATION]

Prometheus Kea Exporter flags:

--prometheus-kea-exporter-address=

Specifies the IP address or hostname on which the agent exports Kea statistics to Prometheus. The default is 0.0.0.0. [STORK_AGENT_PROMETHEUS_KEA_EXPORTER_ADDRESS]

--prometheus-kea-exporter-port=

Specifies the port on which the agent exports Kea statistics to Prometheus. The default is 9547. [STORK_AGENT_PROMETHEUS_KEA_EXPORTER_PORT]

--prometheus-kea-exporter-interval=

Specifies how often the agent collects statistics from Kea, in seconds. The default is 10. [STORK_AGENT_PROMETHEUS_KEA_EXPORTER_INTERVAL]

--prometheus-kea-exporter-per-subnet-stats=

Enable or disable collecting per subnet stats from Kea. The default is true. [STORK_AGENT_PROMETHEUS_KEA_EXPORTER_PER_SUBNET_STATS]

Prometheus BIND 9 Exporter flags:

--prometheus-bind9-exporter-address=

Specifies the IP address or hostname on which the agent exports BIND 9 statistics to Prometheus. The default is 0.0.0.0. [STORK_AGENT_PROMETHEUS_BIND9_EXPORTER_ADDRESS]

--prometheus-bind9-exporter-port=

Specifies the port on which the agent exports BIND 9 statistics to Prometheus. The default is 9119. [STORK_AGENT_PROMETHEUS_BIND9_EXPORTER_PORT]

Stork logs at INFO level by default. Other levels can be configured using the STORK_LOG_LEVEL variable. Allowed values are: DEBUG, INFO, WARN, ERROR.

To control the logging colorization, Stork supports the CLICOLOR and CLICOLOR_FORCE standard UNIX environment variables. Use CLICOLOR_FORCE to enforce enabling or disabling the ANSI colors usage. Set CLICOLOR to 0 or false to disable colorization even if the TTY is attached.

The highest priority always have the command line flags. The parameters from the environment file take precedence over the environment variables if the --use-env-file flag is used.

7.2.4 Registration

The `register` command runs the agent registration using a specified server token and exits. After the successful registration, run the agent normally. The `register` command takes the following arguments:

- u|--server-url=**
Specifies a URL of the Stork Server receiving the registration request. [`$STORK_AGENT_SERVER_URL`]
- t|--server-token=**
Specifies the access token used by the Stork server to allow registration of the Stork agents. [`$STORK_AGENT_SERVER_TOKEN`]
- a|--agent-host=**
Specifies an IP address or DNS name the host where the agent is running. The specified value must include a port number, e.g.: 10.11.12.13:8080. [`$STORK_AGENT_HOST`]
- h|--help**
Returns register command's parameters.

7.2.5 Mailing Lists and Support

There are public mailing lists available for the Stork project. **stork-users** (stork-users at lists.isc.org) is intended for Stork users. **stork-dev** (stork-dev at lists.isc.org) is intended for Stork developers, prospective contributors, and other advanced users. The lists are available at <https://www.isc.org/maillinglists>. The community provides best-effort support on both of those lists.

7.2.6 History

`stork-agent` was first coded in November 2019 by Michal Nowikowski.

7.2.7 See Also

`stork-server(8)`

7.3 stork-tool - A Tool for Managing Stork Server

7.3.1 Synopsis

stork-tool [**global options**] **command** [**command options**]

7.3.2 Description

`stork-tool` provides three features:

- Certificate management - it allows the Stork server to export keys, certificates and tokens that are used to secure communication between Stork server and Stork agents.
- Database Creation - it facilitates creating a new database for the Stork Server, and a user that can access this database with a generated password

- Database migration - it allows database schema migrations to be performed, overwriting the database schema version and getting its current value. There is normally no need to use this, as the Stork server always runs the migration scripts on startup.

7.3.3 Certificate Management

`stork-tool` takes the following arguments (equivalent environment variables are listed in square brackets, where applicable):

- `cert-export` Exports a certificate or other secret data. The options are:
 - `-f|--object=`
Specifies the object to dump, which can be one of `cakey`, `cacert`, `srvkey`, `svrcert`, or `srvtkn`. [`$STORK_TOOL_CERT_OBJECT`]
 - `-o|--file=`
Specifies the location of the file where the object should be saved. [`$STORK_TOOL_CERT_FILE`]

To print the Certificate Authority key in the console:

```
$ stork-tool cert-export --db-url postgresql://user:pass@localhost/dbname -f cakey
INFO[2021-05-25 12:36:07]      connection.go:59      checking connection to database
INFO[2021-05-25 12:36:07]      certs.go:225      CA key:
-----BEGIN PRIVATE KEY-----
MIGHAgEAMBMGBYqGSM49AgEGCCqGSM49AwEHBG0wawIBAQQghrTv9SVZ/hv0xSM+
jvUk+VehIcf1tD/yMfAF4IiVXaahRANCAATgene6dVwo1xCmYjMKYxSrxgOWRm2G
R5X1x72axq2cAhCFm7EpD88oYZ3EBdoXmG9fihV5ZGtfFkSpIdzCNPQI
-----END PRIVATE KEY-----
```

To export the server certificate to a file:

```
$ stork-tool cert-export --db-url postgresql://user:pass@localhost/dbname -f svrcert
↪svrcert -o srv-cert.pem
INFO[2021-05-25 12:36:46]      connection.go:59      checking connection to database
INFO[2021-05-25 12:36:46]      certs.go:221      server cert saved to file: srv-
↪cert.pem
```

- `cert-import` Imports a certificate or other secret data. The options are:
 - `-f|--object=`
Specifies the object to dump, which can be one of `cakey`, `cacert`, `srvkey`, `svrcert`, or `srvtkn`. [`$STORK_TOOL_CERT_OBJECT`]
 - `-i, --file=` Specifies the location of the file from which the object is loaded. [`$STORK_TOOL_CERT_FILE`]

To read the server token from stdin:

```
$ echo abc | stork-tool cert-import --db-url postgresql://user:pass@localhost/
↪dbname -f srvtkn
INFO[2021-08-11 13:31:55]      connection.go:59      checking connection to database
INFO[2021-08-11 13:31:55]      certs.go:259      reading server token from stdin
INFO[2021-08-11 13:31:55]      certs.go:261      server token read from stdin, length
↪length 4
```

To import the server certificate from a file:

```
$ stork-tool cert-import --db-url postgresql://user:pass@localhost/dbname -f
↪srvcert -i srv.cert
INFO[2021-08-11 15:22:28]      connection.go:59    checking connection to database
INFO[2021-08-11 15:22:28]      certs.go:257       server cert loaded from srv.
↪cert file, length 14
```

7.3.4 Database Creation

stork-tool offers the following commands for creating the database for the Stork Server:

- **db-create** Create new database
- **db-password-gen** Generate random database password

Options specific to db-create command:

- m, --db-maintenance-name**
Existing maintenance database name. The default is “postgres”. [\$STORK_DATABASE_MAINTENANCE_NAME]
- a, --db-maintenance-user**
Database administrator user name. The default is “postgres”. [\$STORK_DATABASE_MAINTENANCE_USER_NAME]
- db-maintenance-password**
Database administrator password; if not specified, the user will be prompted for the password if necessary. [\$STORK_DATABASE_MAINTENANCE_PASSWORD]
- f, --force**
Recreate the database and the user if they exist. The default is false.

7.3.4.1 Examples

Create a new database stork with user stork and a generated password:

```
$ stork-tool db-create --db-maintenance-user postgres --db-name stork --db-user stork
INFO[2022-01-25 17:04:56]      main.go:145    created database and user for the
↪server with the following credentials database_name=stork
↪password=L82B+kJE0yhDoMnZf9qPAGyKjH5Qo/Xb user=stork
```

When a database is created using psql tool, it is sometimes useful to generate a hard-to-guess password for this database:

```
$ stork-tool db-password-gen
INFO[2022-01-25 17:56:31]      main.go:157    generated new database password
↪password=znYDfWzvMhWRZyJJuu3EvUxH5KMi1Sm]
```

7.3.5 Database Migration

stork-tool offers the following commands:

- **db-init** Creates a schema versioning table in the database.
- **db-up** Runs all available migrations; use **-t** to migrate to a specific version.
- **db-down** Reverts the last migration; use **-t** to migrate to a specific version.
- **db-reset** Reverts all migrations.
- **db-version** Prints the current migration version.
- **db-set-version** Sets the database version without running migrations.

The following option is specific to the **db-up**, **db-down**, and **db-set-version** commands:

-t|--version=

Specifies the target database schema version. The default is **stork**. [**\$STORK_TOOL_DB_VERSION**]

To initialize a database schema:

```
$ STORK_DATABASE_PASSWORD=pass stork-tool db-init -u user -d dbname
INFO[2021-05-25 12:30:53]      connection.go:59   checking connection to database
INFO[2021-05-25 12:30:53]      main.go:100      Database version is 0 (new version
↪33 available)
```

To overwrite the current schema version to an arbitrary value:

```
$ STORK_DATABASE_PASSWORD=pass stork-tool db-set-version -u user -d dbname -t 42
INFO[2021-05-25 12:31:30]      main.go:77      Requested setting version to 42
INFO[2021-05-25 12:31:30]      connection.go:59   checking connection to database
INFO[2021-05-25 12:31:30]      main.go:94      Migrated database from version 0 to
↪42
```

7.3.6 Common Options

The following options pertain to both **db-** and **cert-** commands:

--db-url=

Specifies the URL for the Stork PostgreSQL database. It's mutually exclusive with the host, port, username, and password. [**\$STORK_DATABASE_URL**]

-u|--db-user=

Specifies the user name for database connections. The default is **stork**. [**\$STORK_DATABASE_USER_NAME**]

--db-password=

Specifies the database password for database connections. If not specified, the user will be prompted for the password if necessary. [**\$STORK_DATABASE_PASSWORD**]

--db-host=

Specifies the name of the host, IP address or a socket path for the database connection. The default value depends on the system. [**\$STORK_DATABASE_HOST**]

-p|--db-port=

Specifies the port on which the database is available. The default is 5432. [**\$STORK_DATABASE_PORT**]

-d|--db-name=

Specifies the name of the database to connect to. The default is **stork**. [**\$STORK_DATABASE_NAME**]

--db-sslmode

Specifies the SSL mode for connecting to the database; possible values are **disable**, **require**, **verify-ca**, or **verify-full**. The default is **disable**. [`$STORK_DATABASE_SSLMODE`] Acceptable values are:

disable Disables encryption between the Stork server and the PostgreSQL database.

require Uses secure communication but does not verify the server's identity, unless the root certificate location is specified and that certificate exists. If the root certificate exists, the behavior is the same as in the case of **verify-ca**.

verify-ca Uses secure communication and verifies the server's identity by checking it against the root certificate stored on the Stork server machine.

verify-full Uses secure communication and verifies the server's identity against the root certificate. In addition, checks that the server hostname matches the name stored in the certificate.

--db-sslcert

Specifies the location of the SSL certificate used by the server to connect to the database. [`$STORK_DATABASE_SSLCERT`]

--db-sslkey

Specifies the location of the SSL key used by the server to connect to the database. [`$STORK_DATABASE_SSLKEY`]

--db-sslrootcert

Specifies the location of the root certificate file used to verify the database server's certificate. [`$STORK_DATABASE_SSLROOTCERT`]

--db-trace-queries=

Enables tracing of SQL queries. Possible values are **run** - only runtime, without migrations, **all** - both migrations and runtime, or **none** - disable the query logging. [`$STORK_DATABASE_TRACE_QUERIES`]

-h|--help

Shows a help message.

Note that there is no argument for the database password, as the command-line arguments can sometimes be seen by other users. It can be passed using the `STORK_DATABASE_PASSWORD` variable.

Stork logs on INFO level by default. Other levels can be configured using the `STORK_LOG_LEVEL` variable. Allowed values are: **DEBUG**, **INFO**, **WARN**, **ERROR**.

To control the logging colorization, Stork supports the `CLICOLOR` and `CLICOLOR_FORCE` standard UNIX environment variables. Use `CLICOLOR_FORCE` to enforce enabling or disabling the ANSI colors usage. Set `CLICOLOR` to `0` or `false` to disable colorization even if the TTY is attached.

7.3.7 Mailing Lists and Support

There are public mailing lists available for the Stork project. **stork-users** (stork-users at lists.isc.org) is intended for Stork users. **stork-dev** (stork-dev at lists.isc.org) is intended for Stork developers, prospective contributors, and other advanced users. The lists are available at <https://www.isc.org/maillinglists>. The community provides best-effort support on both of those lists.

7.3.8 History

`stork-tool` was first coded in October 2019 by Marcin Siodelski; at that time it was called `stork-db-migrate`. In 2021, it was refactored as `stork-tool` and commands for Certificate Management were added by Michal Nowikowski.

7.3.9 See Also

stork-agent(8), *stork-server(8)*